

LEonard

User Manual



LECKY
ENGINEERING

LEonard User Manual

LEonard Software by Lecky Engineering, LLC

Document Version	Date	Major Additions
21.11.4.0	11/04/2021	Initial user interface and device management system, Java interpreter
22.04.1.0	04/01/2022	Universal Robot interface and grinding system, LEScript support
22.08.1.0	08/15/2022	LMI Gocator interface and demonstration
22.11.1.0	11/14/2022	Python support, screen sizing and display management
22.11.1.1	11/25/2022	Documentation fixes, small code cleanup and reorganization

CONTENTS

OVERVIEW	5
THE LEONARD SCREEN.....	6
AN INTRODUCTION TO LEONARD DEVICES	7
THE LEONARDSTATEMENT AND LEONARDMESSAGE.....	9
ALL ABOUT LEONARD SEQUENCE PROGRAMMING	11
THEORY OF OPERATION.....	11
HELLO, WORLD!.....	13
LESRIPT.....	13
JAVA.....	14
PYTHON.....	14
THE MAIN LEONARD TABS	16
RUN TAB.....	17
CODE TAB	19
<i>Code / Positions.....</i>	<i>19</i>
<i>Code / Variables.....</i>	<i>20</i>
<i>Code / Java.....</i>	<i>21</i>
<i>Code / Python.....</i>	<i>22</i>
<i>Code / Manual.....</i>	<i>23</i>
SETUP TAB.....	24
<i>Setup / Devices</i>	<i>25</i>
<i>Setup / Displays.....</i>	<i>28</i>
<i>Setup / Tools.....</i>	<i>29</i>
<i>Setup / Robot.....</i>	<i>31</i>
<i>Setup / General.....</i>	<i>33</i>
<i>Setup / License</i>	<i>33</i>
LOGS TAB.....	34
LEONARD STATEMENTS.....	36
LELIB STANDARD LIBRARY, ALL LANGUAGES	36
<i>Language Control.....</i>	<i>36</i>
using_lescript().....	36
using_java()	36
using_python()	36
exec_lescript(string filename)	36
exec_java(string filename)	37
exec_python(string filename)	37
execline_lescript(string line).....	37
execline_java(string line).....	37
execline_python(string line).....	37
<i>Variables and Data Structures.....</i>	<i>37</i>
<i>LEScript Variable Handling.....</i>	<i>37</i>
le_clear_variables()	37
le_import_variables(filename).....	38

LEonard User Manual

le_system_variable(var_name, True False).....	38
le_random(int N, double low, double high).....	38
LEScript Assignment.....	38
<i>Copying Variables Between LEonard and Java/Python</i>	38
string le_read_var(var_name).....	39
le_write_var(string var_name, string value).....	39
le_write_sysvar(string var_name, string value).....	39
<i>LElib.console: Console Functions</i>	39
le_print(string message).....	39
le_show_console(bool show?).....	39
le_clear_console().....	39
<i>LElib.log: Logging Functions</i>	40
le_log_info(string message).....	40
le_log_error(string message).....	40
<i>LElib.flow: Flow Control Functions</i>	40
comments.....	40
le_pause().....	40
le_stop().....	40
le_prompt(string message).....	41
label_name:.....	41
jump(string labelName).....	41
jumpif(bool condition, string labelName).....	41
call(string labelName).....	41
callif(bool condition, string labelName).....	41
ret().....	41
jump_gt_zero(string varName, string label).....	41
assertTrue(bool condition).....	41
assertFalse(bool condition).....	42
assertEqual(variable_name, value).....	42
assertNotEqual(variable_name, value).....	42
sleep(double timeout_s).....	42
<i>LElib.device: Device Control Functions</i>	42
le_connect(string device_name).....	42
le_disconnect(string device_name).....	42
le_connect_all().....	42
le_disconnect_all().....	42
le_send(string device_name, string message).....	42
string le_ask(string device_name, string message, double timeout_ms).....	43
<i>LElib.infile: Using Input Files</i>	43
infile_open(string filename).....	43
infile_close().....	43
infile_readline().....	43
infile_scale().....	43

Overview

Welcome! LEonard is a work cell control program that maintains communication with all the devices in your industrial work cell and allows you to orchestrate their coordinated operation using simple scripting- just like a good orchestra conductor.

LEonard allows you to write work cell control Sequences in LEScript, Java, or Python. You can also use Java and Python to create complex programs and subroutines that the LEonard Sequence calls, so LEonard doesn't trap you in someone else's framework. The use of Java and Python opens the potential to use millions of lines of pre-existing code, as well as providing you with all the features of these rich programming environments.

LEonard is designed to talk to a variety of devices and allow you to coordinate all of them through a single script. LEonard's tested and validated devices include:

- Robots
 - Universal Robots
- Vision Systems
 - LMI Gocator
 - MVTec HALCON
 - Teledyne Sherlock
 - Cognex Insight
- ID Readers
 - Keyence
 - Cognex Dataman
 - Zebra FS40
- PLC Interfaces (In test)
 - SIPC
 - MODBUS
- External Devices
 - TCP Connections
 - Serial Data

Really, anything you can talk to with Java or Python is a candidate for adding in yourself! Lecky Engineering adds custom device interfaces at customer request. These are usually very simple code extensions to develop, often identical to or very similar to something we already have.

Ask us!

The LEonard Screen

Why does it look like this?




Figure 1 Typical LEonard Main Screen

LEonard is industrial control software and is designed to work well on standard 10" industrial touch screen tablets. Buttons are large and easy to read and special file open and save dialogs, as well as numeric entry, are handled in a touchscreen-friendly way.

LEonard can also be used comfortably on larger monitors. The screen, all the dialogs, and even the font sizes automatically scale as you use different screen sizes or resize the application window.

LEonard provides a standard database of various fixed screen sizes and behaviors, and you can add your own.

More information on LEonard displays is provided in the [Setup | Displays](#) section of the manual

An Introduction to LEonard Devices

LEonard maintains a list of devices that it communicates with. Devices are managed under the **Setup | Devices** tab.




Figure 2 LEonard Setup | Devices Screen

Each device has many setup parameters that control how LEonard accesses and communicates with the device.

The device parameters are explained in more detail in [Setup | Devices](#). It is sufficient to know the following:

- 1) The list of connected devices is stored in a device file. You can have many of these, but most users will need only one.
- 2) Each device has a unique ID number and a unique name.
- 3) Devices can be enabled or disabled... this affects which devices get connected by the **Connect All** button.
- 4) There are several types of devices:
 - a. TcpServer
 - b. TcpClient
 - c. Serial
 - d. Null

- e. Specialty
 - i. Universal Robot Dashboard: UrDashboard
 - ii. Universal Robot Command: UrCommand
 - iii. LMI Gocator Interface: UrGocator
- 5) Each device sets up a **CallBack** function, which is code to handle messages from the device whenever they arrive.

The `general` CallBack is most common and is one of LEonard's key features and tricks! More information on the specifics of the Devices features of LEonard are available in [Setup | Devices](#).

The LEonardStatement and LEonardMessage

Making LEonard send some particular message to some particular device doesn't take much fancy code. You just shoot the characters out some communication port and send some desired terminator.

The fancy part comes in dealing with what comes back. LEonard allows a `CallBack` function to be attached to any device, and most devices will be setup with the standard `general` `CallBack`.

The `general` `CallBack` knows how to interpret what it receives, whenever it receives it. This means that external devices can send messages to LEonard whenever they want.

The received messages need to be what is called a **LEonardMessage**... a series of **LEonardStatements** separated by some separation character.

When a **LEonardStatement** is analyzed, it is expected to be any one of the following. These are checked in sequence and the first match is handled and the other options untested.

- | | |
|------------------------------------|--|
| 1) <code>filename.js</code> | Execute an entire Java file (wow!) |
| 2) <code>filename.py</code> | Execute an entire Python file (wow!) |
| 3) <code>LE:script</code> | Execute any LEScript statement |
| 4) <code>JE:script</code> | Execute any Java statement |
| 5) <code>PE:script</code> | Execute any Python statement |
| 6) <code>SET var_name value</code> | Set <code>var_name = value</code> all languages |
| 7) <code>GET var_name.</code> | Return the current value of variable <code>var_name</code> |
| 8) <code>var_name = value</code> | Stores <code>value</code> into <code>var_name</code> for all languages |

That last one is simple and crucial: remote devices that can send results with `var_name=` in front of each one are instantly integrated into LEonard. This covers most barcode readers, vision systems, and even robots.

As you can see, external devices can ask LEonard to do very complicated or special things. This is what makes it possible to use LEonard to automate so many work cell scenarios.

So, the **LEonardMessage** is simply one or more of these **LEonardStatements** glued together with some sort of character separator, which is `#` by default.

Single: `LEonardMessage<TERM>`
Double: `LEonardMessage<SEP>LEonardMessage<TERM>`
More: `LEonardMessage<SEP>LEonardMessage<SEP> ... <TERM>`

Why do this? The advantage of a multiple statement message is that all the received messages will be executed by LEonard in rapid sequence as a unit. This helps avoid certain kinds of machine race conditions.

What if I don't want this powerful receive capability on certain devices?

To use LEonardStatements, the `general` Callback must be selected by the device. Not using a Callback is the easiest way to prevent devices from asking LEonard to do fancy things when that's not needed or appropriate.

All About LEonard Sequence Programming

Theory of Operation

The Sequence



The screenshot displays the LEonard control interface. On the left, a code editor shows a sequence of Python commands for setting up a coupon inspection. A blue arrow points from the text 'The Sequence' to the 'Start' button. The right side of the interface shows real-time status information, including current time, start time, total run time, and a 'STOPPED' status. Below this, there are buttons for 'gocator_mount' and 'gocator_home', and a 'Touch OFF Grind OFF' button. The bottom of the interface shows the current tool ('gocator3210') and part geometry ('CYLINDER').

```
# 00p Set Origin
exec_python(Lib/leGocatorSupport.py)
using_python()

# Coupon is 762mm diam (32in)
coupon_diameter = 762.0

select_tool('gocator3210')
set_part_geometry('CYLINDER', coupon_diameter)

start_operation()

# Force all speeds and accelerations to good inspection ones!
linear_speed = 100
linear_accel = 100
joint_speed = 20
joint_accel = 10
blend_radius = 2

set_linear_speed(linear_speed)
set_linear_accel(linear_accel)
set_joint_speed(joint_speed)
set_joint_accel(joint_accel)
```

Current Time: 11/13/2022 2:39:49 PM
 Start Time: 11/13/2022 1:52:08 PM
 Total Run Time: 00h 11m 53.8s
STOPPED
 066: movel_incr_part(0,0,0.030,0,0,0)

Time in Step: 00h 00m 02.4s
 Time Estimate: 00h 00m 00.0s
 Time Remaining: 00h 00m 02.4s OVER
 Grind Cycle: of
 Last Z Force: -0.1 N

Joint Move to Tool Mount Pose: gocator_mount
 Joint Move to Tool Home Pose: gocator_home

Start Step Pause Stop Touch OFF Grind OFF gocator3210 CYLINDER 762 dia (mm)
 Tool Part Geom

ENGINEERING User
 Dashboard OK Command Ready
 Robotmode: RUNNING Robot Ready
 Safetystatus: NORMAL 871 871
 PLAYING LEonard01.urp Grind Ready Grind Process
 Gocator OK Gocator Ready

LEonard Rev 22.11.1.0 DEBUG
 11/13/2022 2:39:49 PM

Figure 3 Where is the Main Sequence?

LEonard orchestrates the interoperation of many devices using a **Sequence**, a simple program script that can be written in LScript, Java, Python, or a combination of all three.

All three languages are provided to make things easier for you. Use what you like.

LEonard executes the main **Sequence one line at a time**. This permits monitoring, error recovery, and single stepping.

This may seem odd to those with a formal Computer Science background, but for reasons of safety and error-recovery, each line of a work cell Sequence needs to be handled all on its own.

This also allows single stepping through work cell operations, critical during debug and testing.

Line execution rate is slow, perhaps 10 lines per second. But work cell lines are asking robots and vision systems to do things that typically take many seconds so this doesn't matter.

Wait! What if I want to read the same barcode reader 10 times and return the highest confidence reading?

Just do it in Java or Python. Those languages run at full speed, you can build a function, and then you can just call it from your Sequence.

Large functions that are safe and which don't make robots fly around can be built into Java or Python procedures that you load at the start of the LEonard Sequence. This way, you can go fast when you need to if the error conditions don't create unsafe machine situations. Use your judgement. LEonard won't get in your way or second-guess you.

Now, since LEonard executes Java and Python line-at-a-time in the main Sequence window, creating functions and classes in Java or Python must be done in a separate stand-alone file and loaded in your main program. LEonard provides Java and Python sandboxes for writing and testing standalone code in the **Code | Java** and **Code | Python** tabs.

Hello, World!

How do we `printf("Hello, World!\n");` in a LEonard Sequence?

Well, first, about printing. LEonard provides a unified print console for debugging. Show or hide the console with the F12 key.




Figure 4 LEonard Console Window

Pressing F12 repeatedly shows and hides the console. It is always receiving and buffering print data. All print data goes to the log files, too, in case you ever need to look for that. (You can also use `le_log_error(message)` and `le_log_info(message)` to send things to the log files. More on that in the [Logs](#) tab!)

The Sequence command `le_show_console(True | False)` will also show or hide the console and works in any language.

To send data to the print console, use `le_print(message)` from any language.

OK, now we can try that Hello, World!

LEScript

LEScript is a simple scripting language created by Lecky Engineering that allows “programming-free” interaction with devices. Most typical work cells can be programmed in LEScript. If you need to compute values or get into deeper calculations or manage data structures, think about using Java or Python.

```
# Hello, World! In LEScript
using_lescript() # Redundant since LEScript is default
le_print(Hello, World!)
value = 13.25
```

```
le_print(value = {value})
```

Console Output:
Hello, World!
value = 13.25

Java

LEonard provides a Java interface with full ECMA 5.1 compliance based on **Jint**.

Java Specifications:

Jint Version: 2.11.58
Author: Sebastian Ros
License: <https://raw.githubusercontent.com/sebastienros/jint/master/LICENSE.txt>
Date Published: 11/27/2017
Project URL: <https://github.com/sebastienros/jint>

There are several ways that Java execution can be triggered in LEonard.

1. In a LEonard Sequence, commands are interpreted as LScript until `using_java()` is encountered. Subsequent lines will be executed using Jint.
2. The Sequence function `exec_java(filename)` will run a Java `.js` file as specified.
3. An external device that is using the `general` Callback can return a Java request.
 - a. `Filename.js` The specified file will be executed by Jint
 - b. `JE:javascript` The specified Java commands will be executed by LEonard
4. The test area in the **Code | Java** tab. This provides a “sandbox” where Java programs can be created, edited, saved, and retrieved.

```
# Hello, World! In Java
using_java()
le_print('Hello, World!')
value = 13.25 * 8.1
le_print('value = ' + value)
```

Console Output:
Hello, World!
value = 107.32499999999999

Python

LEonard provides the open-source Iron Python implementation originally developed by Microsoft. This supports Python 2.7 environment and includes the entire standard library. Iron Python support for Python 3 is still in Beta and will be made available upon request if we feel it gets more stable! The Python standard library for 2.7 is quite complete. Import away!

Python Specifications:

Iron Python Version: 2.7.12

Author: Iron Python contributors, Microsoft

License: <https://licenses.nuget.org/Apache-2.0>

Date Published: 1/21/2022

Project URL: <https://ironpython.net/>

There are several ways that Python execution can be triggered in LEonard.

5. In the LEonard Sequence, commands are interpreted as LEScript until `using_python()` is encountered. Subsequent lines will be executed in Python.
6. The Sequence function `exec_python(filename)` will run a Python `.py` file as specified.
7. An external device that is using the `general` Callback can return a Python request:
 - a. Send `Filename.py` The specified file will be loaded and executed in Python.
 - b. Send `PE:pythonscript` The specified Python commands will be executed in Python.
8. The test area in the **Code | Python** tab. This provides a “sandbox” where Python programs can be created, edited, saved, and retrieved.

```
# Hello, World! In Python
using_python()
le_print('Hello, World!')
value = 13.25 * 8.1
le_print(str(value))

import math
var3 = {8, 'abc', 3}
le_print('var3 = ' + str(var3))
le_print('The value of PI is approximately
{0:.6f}'.format(math.pi))
```

Console Output:

```
Hello, World!
107.325
var3 = set([3, 8, 'abc'])
The value of PI is approximately 3.141593.
```

The Main Leonard Tabs

Now you've got a feel for the overall approach to LEonard.

Let's go through each tab in the interface and describe what features are available.

In the main LEonard screen, there are four main operation tabs: **Run**, **Code**, **Setup**, and **Logs**. These tabs are described below.

Many functions can be manually activated with buttons or automatically activated with program commands. The convention in this manual is the used boldface for buttons and Tabs and `Courier Font` for program commands, as in **This Is a Button** and `this_is_a_code_function(param1)`.

The four main tabs will be described below. Here are some quick links if you want to jump!

[Run Tab](#)

[Code Tab](#)

[Setup Tab](#)

[Logs Tab](#)

Run Tab

The **Run** tab is where the bulk of program execution will typically be observed. Different annunciators that show status and control buttons appear on the Run Tab depending on what kinds of devices you are connected to.

For example, the raw LEonard screen looks like this, only showing the main program and providing access to Start, Stop, etc.




Figure 5 LEonard Run Screen with No Options Installed

A program is loaded using the **Program Name** button up next to the **Logs** tab.

Program file operations in addition to **Load** are **New**, **Save**, **Save As**.

To prevent unintentional setup changes or Sequence edits, LEonard provides three **User Modes**.

The user mode is selected using the **User** field in the upper-right corner of the **Run** tab.

1. **Operator** mode only permits loading and running existing Sequences from the **Run** tab. There is no access to the **Code** or **Setup** tabs.
2. **Editor** mode allows access to the **Code** tab to permit editing, but **Setup** is suppressed.
3. **Engineering** mode provides full access to all functions including **Setup**.

Entering Operator or Engineering mode requires a fixed password. By default, these are 9 and 99, respectively.

Code Tab

The **Code Tab** has five sub tabs: **Positions**, for teaching and manually moving to fixed positions, **Variables**, for monitoring or changing LEonard variables, **Java**, for writing and testing Java programs, **Python**, for writing and testing Python programs, and **Manual**, to provide access to documentation. The current software version is always displayed in the lower right of the screen.

Code | Positions

Below is the **Program Tab** when the Positions Subtab is selected.

The screenshot shows the LEonard software interface. At the top is a menu bar with options: Run, Code, Setup, Logs, 00p Origin, New, Save, Save As..., Jog Robot, Door Closed, Pedal Up, and Exit. Below the menu bar is a toolbar with buttons: Linear Move to Pose, Joint Move to Position, Set Position, and Jog Only. The main area is divided into two panes. The left pane shows a Python script for setting up the origin and defining positions. The right pane shows a list of positions with their coordinates. At the bottom, there is a jog screen with buttons for Start, Step, Pause, Stop, Touch OFF, Grind OFF, and fields for Tool (gocator3210), Part Geom (CYLINDER), and diameter (762 mm). The bottom right corner displays the software version (LEonard Rev 22.11.1.0) and the date/time (11/14/2022 3:54:39 PM).

```
# 00p Set Origin
exec_python(Lib/leGocatorSupport.py)
using_python()

# Coupon is 762mm diam (32in)
coupon_diameter = 762.0

select_tool('gocator3210')
set_part_geometry('CYLINDER', coupon_diameter)

start_operation()

# Force all speeds and accelerations
to good inspection ones!
linear_speed = 100
linear_accel = 100
joint_speed = 20
joint_accel = 10
blend_radius = 2

set_linear_speed(linear_speed)
set_linear_accel(linear_accel)
set_joint_speed(joint_speed)
set_joint_accel(joint_accel)
set_blend_radius(blend_radius)
```

Name	Joints
spindle_mount	[-2.68179,-1.90227,-1.42486,-2.95848,-1.70261,0.0009283]
spindle_home	[-2.71839,-0.892528,-2.14111,-3.27621,-1.68817,-0.019554]
sander_mount	[-2.53006,-2.15599,-1.18223,-1.37402,1.57131,0.124]
sander_home	[-2.57091,-0.82644,-2.14277,-1.743,1.57367,-0.999559]
gocator_mount	[-1.994536,-1.693767,-2.011792,-1.301532,1.941065,2.864]
gocator_home	[-0.44141,-1.262893,-2.062313,-1.387395,1.571761,2.7041]
cp_origin	[-0.746832,-1.629936,-1.676383,-1.406107,1.571093,2.426]
grind1	[-0.964841,-1.56224,-2.25801,-2.46721,-0.975704,0.03510]
grind2	[-1.19025,-1.54723,-2.28053,-2.45891,-1.20106,0.0341677]
grind3	[-1.41341,-1.57357,-2.26161,-2.45085,-1.42422,0.0333479]
cp_align_approx	[-1.068756,-1.271386,-2.007839,-1.376935,1.538429,2.103]
cp_align_aligned	[-1.070664,-1.275503,-2.005601,-1.372589,1.537198,2.102]

Figure 6 Code | Positions Tab

Positions can be saved manually (**Set Position**) or from the Sequence with *save_position(name)*.

You can manually move to Positions in Joint (**Joint Move To Position**) or Linear (**Linear Move To Pose**) paths. These can also be executed from a recipe with *move_linear(position)* or *move_joint(position)*.

Jogging is used here for setting or updating named positions or just for moving the robot. This uses the standard Jog screen.

Big Edit opens up a full-screen editor to make editing complex recipes easier.

Code | Variables

Below is the **Program Tab** when the **Variables Subtab** is selected.

The screenshot shows the LEonard software interface with the **Variables Subtab** selected. The interface is divided into several sections:

- Top Bar:** Contains buttons for Run, Code, Setup, Logs, 00p Origin, New, Save, Save As..., Jog Robot, Door Closed, Pedal Up, and Exit.
- Left Pane:** Displays Python code for setting up a coupon inspection. The code includes comments and function calls like `exec_python(Lib/leGocatorSupport.py)`, `using_python()`, `select_tool('gocator3210')`, `set_part_geometry('CYLINDER', coupon_diameter)`, `start_operation()`, and setting various speeds and accelerations.
- Right Pane:** Shows a table of variables. The table has four columns: Name, Value, IsNew, and TimeStamp. The variables listed include `command`, `command_index`, `robot_ready`, `gocator_ready`, `DM1_counter`, `DM1_result`, `DM2_counter`, `DM2_result`, `robot_starting`, `grind_ready`, `grind_contact_enable`, `robot_response`, `robot_completed`, `halt_count`, `grind_cycle`, `grind_process_state`, `robot_linear_speed_mmps`, `robot_linear_accel_mmps`, `robot_blend_radius_mm`, and `robot_joint_speed_dps`.
- Bottom Bar:** Contains buttons for Start, Step, Pause, Stop, and a red 'Touch OFF Grind OFF' button. It also includes dropdown menus for Tool (gocator3210) and Part Geom (CYLINDER), and input fields for diameter (762 mm). The bottom right corner shows the version (LEonard Rev 22.11.1.0) and the date/time (11/14/2022 3:56:05 PM).

Figure 7 Code | Variables Tab

This tab shows all the local variables maintained in LEonard for internal, system, and user purposes. They can be edited here as well.

System variables will not be erased by the **Clear** button, or by the Sequence `le_clear_variables()` command.

The **TimeStamp** shows when the variable was last written.

IsNew indicates whether the variable has ever been examined by the program since the last write.

The variables may be saved or reloaded from Recipes/Variables.xml with the **Save** and **Reload** buttons. Variables are automatically saved on program exit and reloaded when the program starts.

Code | Java

For testing out simple Java programs, the Code | Java tab allows loading, saving, and running Java code using the same Jint Java interpreter and environment used in Sequence execution.

Any code ideas you have can be tried out here prior to building them into an actual Sequence.




Figure 8 Code | Java Test Area

The buttons **New**, **Load**, **Save**, and **Save As...** operate as expected in creating, saving, and loading Java `.js` files.

The **Run** button will execute the Java program displayed immediately, even if LEonard is in the middle of running a Sequence. This is a powerful (maybe too powerful) debug and testing tool.

The bottom-left panel is a copy of any messages sent to `le_print` by Java. The right bottom-right panel shows a list of all Java variables.

Code | Python

For testing out simple Python programs, the Code | Python tab allows loading, saving, and running Python code using the same Iron Python interpreter and environment used in Sequence execution.

Any code ideas you have can be tried out here prior to building them into an actual Sequence.




Figure 9 Code | Python Test Area

The buttons **New**, **Load**, **Save**, and **Save As...** operate as expected in creating, saving, and loading Java `.py` files.

The **Run** button will execute the Python program displayed immediately, even if LEonard is in the middle of running a Sequence. This is a powerful (maybe too powerful) debug and testing tool.

The bottom-left panel is a copy of any messages sent to `le_print` by Python. The right bottom-right panel is currently unused.

Code | Manual

Below is the **Program Tab** when the **Manual Subtab** is selected.




Figure 10 Code | Manual Tab

This tab provides access to all the LEonard manuals as PDF files. They are automatically opened on your system by whatever default application the system uses for PDF files.

There are also desktop shortcuts and Start Menu icons created for all the manuals in the installation process.

Setup Tab

The **Setup Tab** has six sub tabs: **Devices**, **Displays**, **Tools**, **Robots**, **General**, and **License**.

Run

Code

Setup

Logs

00p Origin

New

Save

Save As...

Jog Robot

Door Closed

Pedal Up

Exit

Devices

Displays

Tools

Robots

General

License

Connect

Disconnect

Reconnect

Runtime

Restore

Setup

Restore

Connect All

Disconnect All

Stop

Minimize

Stop

Minimize

ID	Name	Enabled	Connected	DeviceType	Address	MessageTag	CallBack	TxPrefix	TxSuffi»
0	Command	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	TcpServer	127.0.0.1:1000	A.CTL	command		<CR>
1	UR-5eDash	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrDashboard	192.168.0.2:29999	R.Dash			<CR>
2	UR-5eCommand	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrCommand	192.168.0.252:30000	R.Cmd	general		<CR>
3	Gocator	<input type="checkbox"/>	<input type="checkbox"/>	Gocator	192.168.0.3:8190	A.GO	gocator		<CR>
4	GocatorAcc	<input type="checkbox"/>	<input type="checkbox"/>	Gocator	192.168.0.252:8190	A.GO	gocator		<CR>
5	Sherlock	<input type="checkbox"/>	<input type="checkbox"/>	TcpServer	127.0.0.1:20000	A.SH	general		<CR>
6	HALCON	<input type="checkbox"/>	<input type="checkbox"/>	TcpClient	127.0.0.1:21000	A.HA	general		<CR>
7	Keyence	<input type="checkbox"/>	<input type="checkbox"/>	TcpClient	192.168.0.10:8500	AUX2K	general		<CR>
8	Dataman1	<input type="checkbox"/>	<input type="checkbox"/>	Serial	COM3	A.DM1	general		
9	Dataman2	<input type="checkbox"/>	<input type="checkbox"/>	Serial	COM4	A.DM2	general		
10	Chrome	<input type="checkbox"/>	<input type="checkbox"/>	Null		CTL	general		
11	FS40 Control	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	TcpClient	192.168.0.41:107	A.FS40.C	general		<CR><L

Current

C:\Users\Public\LEonard\Config\Default.ldev

Use This File At Startup

☒ Auto Connect On Load

Startup File

C:\Users\Public\LEonard\Config\Default.ldev

Reload

Load

Save

Save As...

Clear

Speed Send Buttons

test

exit

Start

Step

Pause

Stop

Touch OFF

Grind OFF

gocator3210

CYLINDER

762

dia (mm)

Tool

Part Geom

LEonard Rev 22.11.1.0

11/14/2022 4:00:25 PM

Setup | Devices

The LEonard Device list is a datafile created in the `LEonardRoot/Config` directory. You can have several device files and load different ones for different testing or operational situations. One or more Devices files can be created and managed in the **Setup | Devices** tab, shown below.

ID	Name	Enabled	Connected	DeviceType	Address	MessageTag	CallBack	TxPrefix	TxSuffix
0	Command	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	TcpServer	127.0.0.1:1000	A.CTL	command		<CR>
1	UR-5eDash	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrDashboard	192.168.0.2:29999	R.Dash			<CR>
2	UR-5eCommand	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrCommand	192.168.0.252:30000	R.Cmd	general		<CR>
3	Gocator	<input type="checkbox"/>	<input type="checkbox"/>	Gocator	192.168.0.3:8190	A.GO	gocator		<CR>
4	GocatorAcc	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	Gocator	192.168.0.252:8190	A.GO	gocator		<CR>
5	Sherlock	<input type="checkbox"/>	<input type="checkbox"/>	TcpServer	127.0.0.1:20000	A.SH	general		<CR>
6	HALCON	<input type="checkbox"/>	<input type="checkbox"/>	TcpClient	127.0.0.1:21000	A.HA	general		<CR>
7	Keyence	<input type="checkbox"/>	<input type="checkbox"/>	TcpClient	192.168.0.10:8500	AUX2K	general		<CR>
8	Dataman1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	Serial	COM3	A.DM1	general		
9	Dataman2	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	Serial	COM4	A.DM2	general		
10	Chrome	<input type="checkbox"/>	<input type="checkbox"/>	Null		CTL	general		
11	FS40 Control	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	TcpClient	192.168.0.41:107	A.FS40.C	general		<CR><L

Figure 11 LEonard Setup | Devices tab

The **Reload**, **Load**, **Save**, **Save As..** and **Clear** buttons behave as expected. **Clear** also offers an opportunity to create a set of default devices spanning the set of common LEonard devices.

Press **Use This File At Startup** to copy the name of the current file into the **Startup File** field. This will cause that file to be loaded when LEonard starts. If you also select **Auto Connect On Load**, LEonard will attempt to connect to all of the enabled devices in the file at startup.

LEonard devices have the following parameters:

Field Name	Type	Description
ID	Integer	A unique ID assigned to the device
Name	String	A name to help you remember what the device does
Enabled	Boolean	Specifies whether the device should be automatically connected by the Connect All button.

LEonard User Manual

		Devices are also automatically connected when the device file is loaded if Auto Connect On Load is enabled in Setup General
Connected	Boolean	A boolean value
DeviceType	String	One of several classes of devices, discussed below
Address	String	Either IP:Port or COMn
MessageTag	String	A string to be prepended to log messages to help identify messages from a particular device
CallBack	String	A CallBack function, described below.
TxPrefix <PREFIX>	String	A prefix of characters to be sent before each transmission. May include <CR> <LF>, and <CRLF>
TxSuffix <SUFFIX>	String	Characters sent at the end of each transmission. May include <CR> <LF>, and <CRLF>
RxTerminator <TERM>	String	Characters to be waited for to signify end of received message. May include <CR> <LF>, and <CRLF>
RxSeparator <SEP>	String	LEonard will parse (and execute atomically) multiple commands using command<SEP>command<TERM>
OnConnectExec	String	When the external device connects, any LEonardMessage specified here will be executed.
OnDisconnectExec	String	When LEonard initiates a disconnect, any LEonardMessage specified here will be executed.
RuntimeAutostart	Boolean	If true, Runtime Program will be started before connection is attempted. This can be used to start a background server needed by the device for operation.
RuntimeWorkingDirectory	String	The Runtime Program will be executed from this directory
RuntimeFilename	String	Specifies the filename of the Runtime Program
RuntimeArguments	String	Specifies arguments for the Runtime Program
SetupWorkingDirectory	String	Some devices have a Setup Program used to configure them. These can be specified here for directory, filename, and arguments
SetupFilename	String	Filename of the Setup Program
SetupArguments	String	Arguments for the Setup Program
SpeedSendButtons	String	If you'd like to be able to send simple commands for testing to the device, they may be entered here as command1 command2 command3 ... A

LEonard User Manual

		button will be created for each string between vertical bars!
JobFile	String	If a device needs to load a specific program to run it can be specified here. This is currently used by UrDashboard and Gocator to start the specified programs at connect time.
Model	String	If a device returns a model number, it will be entered here
Serial	String	If a device returns a serial number, it will be entered here
Version	String	If a device returns a software version number, it will be entered here

Device Types

LEonard device types must be one of the following items:

1. TcpServer Set up a TCP Server on Address:Port and wait for a connection.
2. TcpClient Immediately connect to a device on Address:Port.
3. Serial Connect to a device with Address = COMn using serial protocol over either a hard serial or a USB serial connection
4. UrDashboard Setup a TCP Client connection to a Universal Robot dashboard server.
5. UrCommand Setup a TCP Server for a Universal Robot PolyScope program to attach to
6. Gocator Setup a TCP Client appropriate for handling commands with an LMI Gocator.
7. Null Connect to nothing... but perhaps use the other features of a device!

Connect/Disconnect Execution

Just after a device connects or just before it is disconnected, LEonard can perform an operation. These operations are encoded in the **OnConnectExec** and **OnDisconnectExec** fields in the device.

Any **LEonardMessage** can be specified. Recall a multi-statement LEonard message can be encoded as:

LEonardMessage = LEonardStatement<SEP>LEonardStatement

Setup | Displays

LEonard maintains a database of standard display sizes in the **Setup | Displays** tab, shown below.

Name	Width	Height	Resizable	Fullscreen	FontScale
Zebra ET80A	2160	1440	<input type="checkbox"/>	<input type="checkbox"/>	100
Zebra L10	1920	1200	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	100
My Laptop	1920	1200	<input type="checkbox"/>	<input type="checkbox"/>	100
Large Monitor	2560	1440	<input type="checkbox"/>	<input checked="" type="checkbox"/>	100
Resize Medium	1800	1000	<input checked="" type="checkbox"/>	<input type="checkbox"/>	100
Resize Fullscreen	1800	1000	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	100

Figure 12 LEonard Setup | Displays Screen

All LEonard windows and dialogs are designed to be resizable. Fonts get larger or smaller as necessary. However, you arrange the dialog to use it, that is how it will appear the next time you see it.

You can create your own display setting, complete with Width, Height, whether the window is fixed size or resizable, whether it should expand to full screen, and an optional additional Font Scale parameter. The **FontScale** is applied to the main windows and all LEonard dialogs.

The display database is automatically saved by LEonard, but you can reload the old one if you've made a mistake. Clearing the displays will also offer an option to restore these defaults.

Whatever display is selected when LEonard exits will be restored at application startup.

Setup | Tools

Tools are defined in the **Setup | Tool** tab, shown below.

Run	Code	Setup	Logs	00p Origin	New	Save	Save As...	Jog Robot	Door Closed	Pedal Up	Exit	
Devices	Displays	Tools	Robots	General	License							
Select	Joint Move to Mount	Joint Move to Home	Tool Test	Tool Off	Cool Test	Cool Off						
Name	x_m	y_m	z_m	rx_rad	ry_rad	rz_rad	mass_kg	cogx_m	cogy_m	cogz_m	ToolOnOuts	ToolOff
gocator3210	0	0	0.381	0	0	-1.57079	1.8	0	0	0.072	2,0	2,0
2F85	0	0	0.175	0	0	0	1	0	0	0.05	2,1,5,1	2,0,5,0
sander	0	0	0.186	0	0	0	2.99	-0.011	0.019	0.067	2,1	2,0
spindle	0	-0.165	0.09	0	2.2214	-2.2214	2.61	-0.004	-0.015	0.049	5,1	5,0
pen	0	-0.08	0.075	0	2.2214	-2.2214	1	-0.004	-0.015	0.049	2,0,5,0	2,0,5,0
pen_SA	0	-0.072	0.103	0	2.2214	-2.2214	0.98	0	0.002	0.048	2,0,5,0	2,0,5,0
none	0	0	0	0	0	0	0	0	0	0		

Set Footswitch Pressed	7,1	Set Door Closed Input	1,1	Reload	Save	Clear
------------------------	-----	-----------------------	-----	--------	------	-------

Start	Step	Pause	Stop	Touch OFF Grind OFF	gocator3210	CYLINDER	762	dia (mm)
				Tool	Part Geom	<small>LEonard Rev 22.11.1.0 11/14/2022 4:02:59 PM</small>		

Figure 13 Setup | Tools Tab

Each tool entry contains the following information. These are saved in the `Tools.xml` file in `LEonardRoot/Config` and are loaded and saved automatically.

1. **Tool TCP:** This is a copy of what we would teach for the tool on the UR including x, y, z offset and rx, ry, rz orientation. Teaching these is best done on the UR and then the values simply copied to the entry in LEonard
2. **Mass and Center of Gravity:** Set these as you would on the UR. Accurate settings improves behavior when in freedrive mode.
3. **ToolOnOuts, ToolOffOuts:** This is a list of up to 4 digital IOs that need to be turned on or off to enable the tool. This is only done during a grind in **Touch ON Grind ON** mode. Examples: "1,1,3,1" implies that output 1 should be set to 1 and output 3 should be set to 1. "3,1" implies that output 3 should be set to 1
4. **CoolantOnOuts, CoolantOffOuts:** Similarly, these are digital output commands to be executed when grinding in **TouchOn Grind ON** mode.
5. **MountPosition:** This is a position recommended for installing/removing this tool. The system will use joint moves to approach the position with **Joint Move To Mount** or

move_tool_mount(). This must be a position that has been defined in the **Positions Table**.

6. **HomePosition:** This is a position recommended for homefor this tool. The system will use joint moves to approach the position with **Joint Move To Home** or *move_tool_home()*. This must be a position that has been defined in the **Positions Table**.
7. **Tool Test, Tool Off** and **Cool Test, Cool Off:** These allow manually verifying the outputs for the currently selected tool.
8. **Set Footswitch Pressed Input:** This is defaulted to 7,1 meaning that input 7 goes high when the footswitch is pressed.
9. **Set Door Closed Input:** This is defaulted to 1,1 meaning that input 1 goes high when the door is closed.

Setup | Robot

Robot and grinding general settings are maintained in the Setup | Robots page, shown below.

Run	Code	Setup	Logs	00p Origin		New	Save	Save As...	Jog Robot	Door Closed	Pedal Up	Exit																							
Devices				Displays				Tools				Robots				General				License															
Grind Trial Speed 100 mm/s				Grind Acceleration 100 mm/s ²				Grind Max Blend Radius 2 mm				Grind Touch Speed 5 mm/s				Grind Touch Retract 3 mm				Grind Force Dwell Time 500 ms				Grind Max Wait Time 1500 ms				Restore Defaults							
Grind Jog Speed 100 mm/s				Grind Jog Accel 400 mm/s ²				Force Damping 0.1				Force Gain Scaling 1								Grind Point Frequency 2 Hz															
Linear Speed 100 mm/s				Joint Speed 20 deg/s				Blend Radius 2 mm				Restore Defaults																							
Linear Acceleration 100 mm/s ²				Joint Acceleration 10 deg/s ²																															
Start				Step				Pause				Stop				Touch OFF Grind OFF				gocator3210				CYLINDER				762				dia (mm)			
																				Tool				Part Geom				LEonard Rev 22.11.1.0 11/14/2022 4:05:36 PM							

Figure 14 Setup | Robots Tab

First, there are settings governing grind operations. These are saved in the `Variables.xml` file in `LEonardRoot/Config` and are sent to the robot whenever the software starts. New values are saved automatically.

Grind Trial Speed: When not in **Touch On Grind On** mode, the grind patterns are limited to one cycle and are performed at this speed.

Grind Acceleration: Linear acceleration used during grinding

Grind Max Blend Radius: Maximum blend radius used during grinding. Recommended 2 mm

Grind Touch Speed: Speed robot advances toward part for touch off. Recommended 5-10 mm/s

Grind Touch Retract: Distance robot retracts from part after touch off.

Grind Force Dwell Time: How long robot waits after turning force-on to allow time for tool to settle against part

Grind Max Wait Time: Maximum time system will wait for the next grind command if a grind command ends with 1 (stay in contact with part)

Grind Jog Speed: Linear speed used for all grinding motions that are not in contact with the part other than the actual simulated grind which runs at **Grind Trial Speed**.

Grind Jog Accel: Linear acceleration used for all grinding motions that are not in contact with the part.

Grind Point Frequency: Used as a minimum frequency for points generated for circles and spirals.

Force Damping: May be useful for force mode tuning in the future. Calls the URScript function `force_mode_set_damping()` with a value between 0 and 1. The default is 0 and that is the only value that has been tested.

Force Gain Scaling: May be useful for force mode tuning in the future. Calls the URScript function `force_mode_set_gain_scaling()` with a value between 0 and 2. The default is 1.0 and that is the only value that has been tested.

Second, there are generally self-explanatory settings for default speeds and accelerations used in basic jogging and non-grinding motion. These are also saved in `Variables.xml`. New values are saved automatically. **Restore Defaults** sets all to standard values used in all testing.

Setup | General

Any system-wide setup is stored in **Setup | General**.

Currently, only the `LEonardRoot` directory is stored here and that is currently defaulted to `C:\Users\Public\LEonard`. This is a good place for LEonard files since any user will be able to access them there.

Setup | License

LEonard shows its licensing information in **Setup | License**. LEonard uses an encrypted license file that includes information about the CPU, Windows Version it is licensed on, and options that are included in the installation.

Devices	Displays	Tools	Grind	General	License
<div>LEonard License File Lecky Engineering LLC c. 2021-2023 Created: 10/22/2022 3:55:18 PM LEONARD VERSION OK LICENSED: 2022.10.10.6 CURRENT: 2022.11.5.10 CPU SERIAL NUMBER OK BFEBFBFF000A0652 WINDOWS GUID OK 2bdc9592-e3ab-4669-a866-af6652c76935 DAYS REMAINING OK PERPETUAL OPTIONS: Java: ENABLED Python: ENABLED Universal Robots: ENABLED Grinding Package: ENABLED Gocator: ENABLED</div>					

Licenses can be perpetual or have a time limit for trial purposes.

A given license file will only work on one CPU and one installation of Windows. Contact Lecky Engineering if you have other needs. We're very flexible.

Current options are:

- Java
- Python
- Universal Robots Support Package
- Grinding Package for Universal Robots
- LMI Gocator Support

Contact Lecky Engineering to enable features and troubleshoot licensing issues on your system.

Figure 15 LEonard Setup | License Viewer

Logs Tab

The Log Tab provides five windows where log messages are displayed. The level of detail in the messages is controlled by the Log Level setting:

- Error: only error messages are shown
- Warn: Error messages and Warnings are shown
- Info: All of the above, plus informational messages about execution. Default setting
- Debug: All of the above plus additional information that may be useful for debugging
- Trace: All of the above plus extremely verbose execution tracing

The **All Log Messages** box gets 100% of the generated messages. These messages are also written to log files in the `LEonardRoot/Logs` directory, where up to forty 25MB files are archived. Information older than this 2GB total is automatically and silently deleted over time.

The screenshot displays the LEonard Logs Tab interface. At the top, a toolbar contains buttons for 'Run', 'Code', 'Setup', 'Logs', '50p Inspect All', 'New', 'Save', 'Save As...', 'Jog Robot', 'Door Closed', 'Pedal Up', and 'Exit'. The main area is divided into several log windows. The 'All Log Messages' window shows a detailed log of system events, including robot movements and tool changes. The 'Exec: Messages Starting With EXEC' window shows a log of execution commands. The 'Errors and Warnings' window displays warning messages about missed responses. The 'Log Level' dropdown is set to 'Info'. The bottom status bar shows 'Start', 'Step', 'Pause', 'Stop', 'Touch OFF', 'Grind OFF', 'gocator3210', 'CYLINDER', '762', 'dia (mm)', and 'LEonard Rev 22.11.1.0 DEBUG 11/13/2022 1:23:56 PM'.

Figure 16 LEonard Logs Tab

In addition, some messages are copied for clarity to other boxes.

1. Any Warning or Error messages are duplicated in the Errors and Warnings box. Warnings are always displayed in Orange, and Errors in Red.
2. Any messages starting with the characters `EXEC` are duplicated in the “Exec: Messages Starting With EXEC” box. These messages are typically associated with Sequence line-

by-line execution. Execution messages generated by LEScript contains “EXECL”. Java and Python execution messages start with “EXECJ” and “EXECP”, respectively.

3. Messages beginning with `R.` are duplicated in the “Robot: Messages starting with R.” box. All devices have a **MessageTag** setup in their **Devices** entry and these characters are always prepended to their messages. Placing all the robot-related messages into a device containing a tag that starts with `R.` causes those messages to be duplicated here. This can help see robot-related issues with your Sequence.
4. Similarly, there is an “Aux: Messages Starting With A.” box. Any messages beginning with `A.` are duplicated here, so assign a **MessageTag** starting with `A.` to any devices whose messages you’d like to see here.

Any of the boxes can be cleared by double-clicking on them. All boxes can be cleared with **Clear All**. All the messages are appended to the log files and are archived as described above.

LEonard Statements

You know all there is to know about the LEonard user interface. Congratulations!

What's left? All the possible Sequence statements and what they do.

This is the comprehensive list.

Certain options, such as Universal Robot or LMI Gocator support, enable other options which are documented in the **Using XXXX with LEonard** manual series.

LElib Standard Library, All Languages

The LElib Library provides common functions across all three languages.

Where differences exist, they are be highlighted with the language matrix shown below.

LEScript	Java	Python
?	?	?

Language Control

By default, all Sequences are interpreted as LEScript. You can change this with the `using_xxx()` functions. The language that is currently being interpreted is always available in the system variable `le_language`.

```
using_lescript()
```

Future sequence lines will be interpreted as LEScript. The variable `le_language` is set to `LEScript` in LEScript, Java, and Python.

```
using_java()
```

Future sequence lines will be interpreted as Java. The variable `le_language` is set to `Java` in LEScript, Java, and Python.

```
using_python()
```

Future sequence lines will be interpreted as LEScript. The variable `le_language` is set to `Python` in LEScript, Java, and Python.

```
exec_lescript(string filename)
```

This command loads an entire LEScript Sequence and executes all lines sequentially. Recommended only for setup purposes to set variables. Should not try to execute long operations like robot moves, but it will if you ask it to!

```
exec_java(string filename)
```

This command loads an entire Java script file and executes it in a fashion identical to the way the **Code | Java** test area does.

```
exec_python(string filename)
```

This command loads an entire Python file and executes it in a fashion identical to the way the **Code | Python** test area does.

```
execline_lescript(string line)
```

This function can be used if you just want to execute one line of LEScript regardless of what language is selected.

```
execline_java(string line)
```

This function can be used if you just want to execute one line of Java regardless of what language is selected.

```
execline_python(string line)
```

This function can be used if you just want to execute one line of Python line regardless of what language is selected.

Variables and Data Structures

This is the area where the three languages supported by LEonard differ the most!

For Java and Python, declaring and setting variables, using math, and creating class and structures works as expected in those languages.

Just remember that the Sequence executes line-by-line, so any multiline definitions need to be placed in a text file and either imported or loaded.

LEScript Variable Handling

LEScript has a few specific variable handling functions which are described below:

```
le_clear_variables()
```

LEScript	Java	Python
X		

Deletes all variables except ones that are marked in the Code | Variables table as system variables.

Variables named robot_* and grind_* are automatically marked as system variables.

You can also use `le_write_sysvar(name, value)` from Java or Python, or `le_system_variable(name, True|False)`, to set whether a variable is a system variable.

`le_import_variables(filename)`

LEScript	Java	Python
X		

Read a file and process any lines that contain `variable_name = value`.

`le_system_variable(var_name, True|False)`

LEScript	Java	Python
X		

Sets whether an existing variable is a system variable.

`le_random(int N, double low, double high)`

LEScript	Java	Python
X		

LEScript doesn't have direct access to the powerful random number facilities of Java or Python. We suggest you use them, but for a basic capability from native LEScript we have `le_random()`.

This function creates `N` variables between `low` and `high` and names them `rnd1`, `rnd2`, through `rndN`.

LEScript Assignment

LEScript supports updating variables using any of these basic operations. For `++`, `--`, `+=`, and `-=`, if the named variable does not exist, it is first created and initialized to 0.

Variables can be substituted into any LEScript command using the syntax `{var_name}`.

```
var_name = 12.3          var_name = {other_var_name}
var_name++              var_name--
var_name -= 17.5        var_name += 18
```

Copying Variables Between LEonard and Java/Python

When a variable is written in LEScript or assigned a value in a LEonardMessage, it is written to the global variable list of all three languages.

Explicitly rereading a variable or writing a variable back to LEScript either as a system variable or a standard variable is support for both Java and Python.

System variables differ from normal variables in that they are not erased by the `le_clear_variables()` function. All variables are written to the data file `LEonardRoot\Config\Variables.xml` when LEonard closes, and so are persistent.

`string le_read_var(var_name)`

LEScript	Java	Python
	X	X

Copies a variable from LEonard to Java or Python. All LEonard variables are stored as strings! Note that when variables are written in LEonard they are automatically also copied to Java and Python.

`le_write_var(string var_name, string value)`

LEScript	Java	Python
	X	X

Copies a variable from Java or Python to LEonard. All LEonard variables are strings.

`le_write_sysvar(string var_name, string value)`

LEScript	Java	Python
	X	X

Copies a variable from Java or Python to LEonard and marks it as a system variable. All LEonard variables are strings.

LElib.console: Console Functions

`le_print(string message)`

Prints message to the Console Window. For Java and Python, it is also sent to the console test areas in **Code | Java** or **Code | Python** as appropriate. The messages are also logged to the logfile as:

```
LEScript:    LPR:message
Java:        JPR:message
Python:      PPR:message
```

`le_show_console(bool show?)`

Hides or shows the Console Window. The console is always open and accumulating any `le_print(...)` messages from any language.

`le_clear_console()`

Clears all the text from the Console Window, just like the **Clear** button in the console window itself.

LElib.log: Logging Functions

```
le_log_info(string message)
```

Send the message to the logging system as Info. The message will appear in the **Logs** tab and in the logfile.

```
le_log_error(string message)
```

Send the message to the logging system as Error. The message will appear in the **Logs** tab in red in the Error buffer and will also be sent to the logfile.

LElib.flow: Flow Control Functions

Flow control in line-by-line execution is implemented differently than it is in the Java or Python standards.

LEonard follows a convention in which lines can be given label names and then jumped to or called. This is consistent with line-by-line execution and is why LEonard is different in the main execution window.

Java and Python functions created in text files operate the way Java and Python always do!

The following sections list each flow control command.

```
comments
```

LEScript comments in the Sequence follow both the Java and Python conventions as follows:

1. All blank lines are skipped
2. Characters after “#” on any line are ignored
3. Characters after “//” on any line are ignored

Java and Python comments are defined as in the respective languages. Python statements ignore characters after “#” on any line and Java statements ignore any characters after “;” on any line.

```
le_pause()
```

Causes execution to pause, just like pressing **Pause** on the Run tab.

```
le_stop()
```

Causes execution to stop, just like pressing **Stop** on the Run tab.


```
le_prompt(string message)
```

Puts up a dialog box containing `message` and pauses execution until the operator presses Continue or Abort.

```
label_name:
```

Yes, this works in all three languages! This helps support line-by-line sequencing and flow control, which Java and Python cannot do.

This structure associates a name with a line in the Sequence. Label names are alphanumeric, case-sensitive, and may include the `'_'` character. Labels are found prior to execution and can be used as targets for `jump`, `jumpif`, `call`, and `callif` statements. LEScript provides the `jump_gt_zero(variable, labelName)` function since it does not presently have the ability to evaluate comparison conditions.

```
jump(string labelName)
```

Causes execution to pass to the line containing `labelName`:

```
jumpif(bool condition, string labelName)
```

Performs a `jump` to the line containing `labelName`: if condition is true.

```
call(string labelName)
```

Causes execution to pass to the line containing `labelName`: Use `ret()` to return from the call. Call maintains a return stack (which is cleared when execution begins!) and can nest.

```
callif(bool condition, string labelName)
```

Performs a `call` to the line containing `labelName`: if condition is true.

```
ret()
```

Return execution from a `call(...)` or `callif(...)` to the line after the one that initiated the call.

```
jump_gt_zero(string varName, string label)
```

Only available in LEScript since traditional Java and Python comparisons aren't available there. Equivalent to `jumpif(var_name > 0, 'label_name')` in either Java or Python.

```
assertTrue(bool condition)
```

Testing support function. Halts execution if condition is not true.

```
assertFalse(bool condition)
```

Testing support function. Halts execution if condition is true.

```
assertEqual(variable_name, value)
```

Testing support function used only in LEScript. Halts execution if `variable_name != value`.

```
assertNotEqual(variable_name, value)
```

Testing support function used only in LEScript. Halts execution if `variable_name == value`.

```
sleep(double timeout_s)
```

Causes the Sequence to pause for `timeout_s` seconds. All other operations continue, so this is better to use than the built-in sleep functions in Java or Python!

LElib.device: Device Control Functions

```
le_connect(string device_name)
```

Performs the **Connect** function on the specified device. Equivalent to selecting the corresponding row in the **Setup | Devices** table and pressing **Connect**.

```
le_disconnect(string device_name)
```

Performs the **Disconnect** function on the specified device. Equivalent to selecting the corresponding row in the **Setup | Devices** table and pressing **Disconnect**.

```
le_connect_all()
```

Performs the **Connect** function on all devices in the **Setup | Devices** table that are enabled. Equivalent to pressing **Setup | Devices | Connect All**.

```
le_disconnect_all()
```

Performs the **Disconnect** function on all connected devices in the **Setup | Devices** table that are enabled. Equivalent to pressing **Setup | Devices | Connect All**.

```
le_send(string device_name, string message)
```

Sends the specified `message` to `dev_name` including any terminators specified in the device entry. Device must be connected.

```
string le_ask(string device_name, string message, double
timeout_ms)
```

Sends the specified message to `dev_name` including any terminators specified in the device entry. Device must be connected.

Waits up to `timeout_ms` for a response and returns it as follows:

1. LEScript. Any response is stored in the variable `le_ask_response`. If no response is received or the device is not connected, sets the return value to `Null`.
2. Java and Python. The received string is returned by the function.

LElib.infile: Using Input Files

Java and Python have extensive file I/O capabilities. This library is a simple set of functions that allow LEScript to read CSV files one line at a time. Deprecated.

LEScript	Java	Python
X		

```
infile_open(string filename)
```

Opens up file `LEonardRoot/Data/filename` for reading. The file is assumed to be in CSV format. Headers are skipped.

```
infile_close()
```

Closes any file that has been opened with `infile_open(...)`.

```
infile_readline()
```

A line is read from the file opened with `infile_open(...)`. Fields found on the line are stored in individual variables named `infile_p0`, `infile_p1`, etc. The values can be automatically scaled using `infile_scale(...)` below.

```
infile_scale()
```

Causes any data subsequently read using `infile_readline()` from specified columns of the input file to be scaled by a value. For example, the line below would cause columns 2, 3, and 4 of the input data to be multiplied by 0.0254, for example to convert from inches to meters.

```
infile_scale(2,0.0254,3,0.0254,4,0.0254)
```

INDEX

LElib.console	
le_clear_console()	39
le_print	39
le_show_console	39
LElib.device	
le_ask	42
le_connect	41
le_connect_all	41
le_disconnect	41
le_disconnect_all	41
le_send	42
LElib.flow	
assert	41
call	40
callif	41
comments	40
jump	40
jump_gt_zero	41
jumpif	40
label_name	40
le_pause	40
le_prompt	40
le_stop	40
ret	41
sleep	41
LElib.infile	
infile_close	42
infile_open	42
infile_readline	42
infile_scale	42
LElib.language	
exec_java	36
exec_python	37
le_language	36
using_java	36
using_lescript	36
using_python	36
LElib.log	
le_log_error	39
le_log_info	39
LElib.variables	
import_variables	38
le_clear_variables	37
le_import_variables	37
le_random	37
le_read_var	38
le_system_variable	37
le_write_sysvar	38

le_write_var38

LEScript Assignment38

system variable37