

Using Universal Robots with LLeonard



LECKY
ENGINEERING

Using Universal Robots with LEonard

LEonard Software by Lecky Engineering, LLC

Document Version	Date	Major Additions
21.11.4.0	11/04/2021	Initial user interface and device management system, Java interpreter
22.04.1.0	04/01/2022	Universal Robot interface and grinding system, LEScript support
22.08.1.0	08/15/2022	LMI Gocator interface and demonstration
22.11.1.0	11/14/2022	Python support, screen sizing and display management

CONTENTS

OVERVIEW	6
BASIC ETHERNET CONNECTION.....	6
THE LEONARD INTERFACE.....	7
INSTALLING PROGRAMS ON THE UR.....	8
<i>Program Installation Method 1: FTP.....</i>	<i>8</i>
<i>Program Installation Method 2: The Supplied Magic File</i>	<i>8</i>
LEONARD.URP COMMUNICATIONS	10
LELIB.UR LIBRARY FOR UNIVERSAL ROBOTS.....	12
LELIB.UR.DASHBOARD: COMMANDS TO CONTROL THE UR DASHBOARD	12
string ur_dashboard(string message, int timeout_ms).....	12
LELIB.UR.ROBOT: THE UR ROBOT POLYSCOPE INTERFACE	14
UR Robot Control Commands.....	Error! Bookmark not defined.
select_tool(string tool_name).....	14
set_part_geometry(string FLAT CYLINDER SPHERE, double part_diam_mm)	14
save_position(position_name).....	14
move_linear(position_name).....	14
move_joint(position_name).....	14
move_relative(dx_mm, dy_mm).....	14
move_tool_home().....	14
move_tool_mount().....	14
free_drive(0=OFF 1=ON).....	14
set_linear_speed(speed_mm/s).....	15
set_linear_accel(accel_mm/s^2)	15
set_joint_speed(speed_deg/s).....	15
set_joint_accel(double accel_deg/s^2)	15
set_blend_radius(double blend_radius_mm).....	15
get_actual_tcp_pose()	15
get_target_tcp_pose()	15
get_actual_joint_positions()	15
get_target_joint_positions()	15
get_actual_both()	15
get_target_both()	16
movej(double j1, j2, j3, j4, j5, j6)	16
movel(double x, y, z, rx, ry, rz).....	16
get_tcp_offset()	16
movel_incr_base(double x,y,z,rx,ry,rz)	16
movel_incr_tool(double x,y,z,rx,ry,rz).....	16
movel_incr_part(x,y,z,rx,ry,rz).....	17
movel_single_axis(axis,value)	17
movel_rot_only(rx,ry,rz)	17
movel_rel_set_tool_origin(double x,y,z,rx,ry,rz).....	17
movel_rel_set_tool_origin_here()	17
movel_rel_tool(x,y,z,rx,ry,rz).....	17
movel_rel_set_part_origin(x,y,z,rx,ry,rz)	17
movel_rel_set_part_origin_here()	17

Using Universal Robots with LLeonard

move_rel_part(x,y,z,rx,ry,rz)	17
send_robot(string message)	17
set_output(int port, bool value)	18
robot_socket_reset()	18
robot_program_exit()	18
set_tcp(x,y,x,rx,ry,rz)	18
set_payload(mass_kg,cog_x_m, cog_y_m, cog_z_m)	18
set_door_closed_input(int dig_in, int state)	18
set_footswitch_pressed_input(int dig_in, int state)	19
set_tool_on_outputs(int dig_out, int state, ...)	19
set_tool_off_outputs(int dig_out, int state, ...)	19
set_coolant_on_outputs(int dig_out, int state, ...)	19
set_coolant_off_outputs(int dig_out, int state, ...)	19
tool_on()	19
tool_off()	19
coolant_on()	19
coolant_off()	19
LELIB.UR.GRIND: THE UR GRINDING PACKAGE	19
grind_line(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_line_deg(length_mm, angle_deg, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_rect(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_serp(dx_mm, dy_mm, n_xsteps, n_ysteps, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_poly(circle_diam_mm, n_sides, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_circle(circle_diam_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_spiral(circle1_diam_mm, grind_circle2_diam_mm, n_spirals, n_cycles, speed_mm/s, force_N, stay_in_contact)	20
grind_retract()	20
grind_contact_enable(0=Touch OFF,Grind OFF 1=Touch ON,Grind OFF 2=Touch ON,Grind ON)	21
grind_touch_retract(touch_retract_mm)	21
grind_touch_speed(touch_speed_mm/s)	21
grind_force_dwell(dwell_time_ms)	21
grind_max_wait(max_time_before_retract_ms)	21
grind_max_blend_radius(grind_blend_radius_mm)	21
grind_trial_speed(trial_speed_mm/s)	21
grind_linear_accel(accel_mm/s^2)	21
grind_point_frequency(point_frequency_hz)	21
grind_jog_speed(trial_speed_mm/s)	21
grind_jog_accel(accel_mm/s^2)	21
grind_force_mode_damping(damping: 0.0 - 1.0)	22
grind_force_mode_gain_scaling(scaling: 0.0 - 2.0)	22
enable_user_timers(integer 0=off, 1=on)	22
zero_user_timers()	22
return_user_timers()	22
LELIB.UR.GRIND GRINDING EXAMPLES	22
Remove Current Tool	22
Install A Tool	23
Integrated Example	23
Computed Concentric Circles	24
Lots of Grinds	25

Overview

LEonard provides a custom interface for industrial cobots from Universal Robots (UR).


The interface is currently in use with UR-5e and UR-10e robots in many places.

For more information and documentation on the exciting UR product line, see www.universal-robots.com.

Basic Ethernet Connection

The UR and the computer running LEonard must have an Ethernet interface capable of communication. At Lecky Engineering, our test machine is on 192.168.0.252/24 and our UR-5e is on 192.168.0.2/24 (`robotIP=192.168.0.2` for us).

You should be able to use `ping robotIP` and `ssh root@robotIP` to verify communication. SSH uses `root` with default password `easybot` on a UR!



```
Command Prompt - ssh root@192.168.0.2
Microsoft Windows [Version 10.0.22621.819]
(c) Microsoft Corporation. All rights reserved.

C:\Users\nedlecky>ping 192.168.0.2

Pinging 192.168.0.2 with 32 bytes of data:
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64

Ping statistics for 192.168.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Users\nedlecky>ssh root@192.168.0.2
root@192.168.0.2's password:
Universal Robots A/S Linux image

Production image
root@ur-20195501059:~# ls
fdisk.script      metadata.n3       polyscope-9.log
firmware          metadata.n3.old  polyscope.log
flightreports     polyscope-10.log putHostnameInHostsFile.py
GUI              polyscope-1.log  robotiq
histogram.properties polyscope-2.log  run_gui.sh
kiosk.sh         polyscope-3.log  starturcontrol.sh
legal_notices    polyscope-4.log  stopurcontrol.sh
list_programs.sh polyscope-5.log  uninstall
log_history.bak  polyscope-6.log  ur-serial
log_history.txt  polyscope-7.log  usbplug.sh
metadata.ini     polyscope-8.log  xsession
root@ur-20195501059:~#
```

Figure 1 Pinging and SSH into a UR to Verify Communication

Using Universal Robots with LLeonard

If you're like us, you may also want to be able to move files on and off your UR easily. We use WinSCP. Just connect your FTP client to `robotIP:22` and use that `root`, `easybot` login to get access.




Figure 2 WinSCP FTP access to a UR

The LLeonard Interface

To communicate with the UR, the **Devices** list in LLeonard needs one or two entries for the robot:

1. If you just want to use the UR Dashboard interface and ask the robot to load/run existing PolyScope programs on the robot, you only need a **UrDashboard** device.
2. If you want to use the Lecky Engineering `LEonard01.urp` PolyScope program that allows commanding, driving, and sequencing the robot, as well as using the Lecky Engineering Grinding programs, you also need a **UrCommand** device.

Both devices connect to the same robot, just on different ports.

1. Port 29999 is a standard fixed port that provides dashboard control services on all UR robots. It connects to the robot as a **TcpClient** but has some special features that a basic **TcpClient** device does not.
2. Port 30000 is a custom port used in the Lecky Engineering `LEonard01.urp` PolyScope program. The program looks for a **TcpServer** on the machine running LLeonard. The UrCommand device is a customized **TcpServer** device that has some special features to help with the UR interface.

Using Universal Robots with LEonard

Devices		Displays	Tools	Robots	General	License															
Connect		Disconnect		Reconnect		Runtime App				Restore		Setup App				Restore		Connect All		Disconnect All	
										Minimize						Minimize					
										Exit						Exit					
	ID	Name		Enabled	Connected	DeviceType	Address			MessageTag		CallBack		TxPrefix	TxSuffix						
	1	UR-5eDash		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrDashboard	192.168.0.2:29999			R.Dash					<C						
	2	UR-5eCommand		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrCommand	192.168.0.252:30000			R.Cmd		general			<C						

Figure 3 Device Entries for Universal Robot

It is important to use the `UrCommand` callback as well as the displayed `TxSuffix` and `RxTerminator`. Default devices that have everything setup just the way we need although you might need to edit the IP address!

The PolyScope job that you wish to be loaded by the `UrDashboard` can be included in the `Jobfile` field of the dashboard device entry. For our example, this is set to `LEonard/LEonard01.urp` since the `LEonard01.urp` program is stored on the robot in `programs/LEonard/LEonard01.urp`.

Installing Programs on the UR

As an aside, how do we get the programs on the UR? The program needs to wind up on the robot in `programs/LEonard`, and the PolyScope program also requires three somewhat complicated URScript programs to support robot and grinding applications.

Program Installation Method 1: FTP

We already discussed one method, FTP. Just copy the files from your PC on `LEonardRoot\3rdParty\UR\USB Image- Program Installer/LEonard` onto the robot in `programs/LEonard`.

Program Installation Method 2: The Supplied Magic File

Another method is to use UR magic files:

1. Make sure your existing robot programs are backed up! This process should not affect them, but it never hurts to be careful.
2. Take a fully erased USB thumb drive and insert it in your PC.
3. Copy all the files and subdirectories from `LEonardRoot\3rdParty\UR\USB Image- Program Installer` onto the thumb drive.
4. Plug the thumb drive into your robot USB port on the pendant- all of the necessary files will be installed on your robot in the `programs/LEonard` directory.

Using Universal Robots with LEonard

You will likely need to manually open `LEonard01.urp` on your robot to associate it with the installation file you are using in your installation. You'll be prompted to select an installation file. Once you do, resave the program and everything should be automatic from there.

There is also a set of three hard-coded IP address that the robot looks at to find LEonard. This allows a robot to be directly tied to only one LEonard. You will have to adjust this if the PolyScope program if your address is something different. Lecky Engineering can help if you need some assistance!

The `LEonard01.urp` PolyScope program currently looks for LEonard on:

`169.254.254.200:30000`

`169.254.254.210:3000`

`192.168.0.252:30000`

Connection is initiated by selecting the desired row and pressing **Connect**. In addition, if you have selected **Auto Connect On Load** for your device file, the connection will be started automatically when LEonard starts.

LEonard always starts a UrDashboard connection with a set of commands to initialize the robot, load any specified program, and start it.

```
close safety popup
is in remote control (response must be true)
if JobFile <> ""
    load <Jobfile> (as in Device... default LEonard/LEonard01.urp
    get loaded program (make sure response matches above)
    play
```

Upon successful connection, the `Connected` field should check itself and the UR Status annunciators should appear on the Run tab.

The Run tab in LEonard uses `robotmode` to determine whether the robot has booted, and regularly sends `robotmode`, `safetystatus`, and `programstate` to keep an eye on the robot.

Using Universal Robots with LEonard




Figure 4 Gocator Status Annunciators

LEonard.urp Communications

The LeckyEngineering PolyScope program supplied for robot sequencing, control, and the grind functions is complex.

Our simple PolyScope program uses large set of underlying URScript code to perform most functions.

That said, UR-savvy users are able to add their own functions to the PolyScope program with relative ease. All communications between LEonard and the PolyScope program happen over a single socket using a message ID, a simple checksum, and the parameters which are all assumed to be numeric.

All return messages from the robot are asynchronous **LEonardMessages** and can set variables or execute LEScript, Java, or Python functions within LEonard. The whole architecture is quite powerful.

If you need to customize `LEonard01.urp` or the underlying URScript code for your own needs, don't hesitate to contact Lecky Engineering for some start-up assistance!

Controlling the Robot

The UR may be commanded from LEScript, Java, or Python with equal ease.

All three languages provide a set of functions that cover most point-to-point, grinding, and inspection tasks that you might want to do with your cell.

LElib.UR Library for Universal Robots

These functions work with Universal Robots robotic systems. The commands fall into three categories

1. Dashboard
2. Command Interface to Lecky Engineering's LEonard01.urp PolyScope program
3. Grinding Package for force-controlled surface following

LElib.UR.dashboard: Commands to control the UR dashboard

The UR robot provides a dashboard interface that allows controlling the robot operation.

```
string ur_dashboard(string message, int timeout_ms)
```

Sends the command `message` to the currently selected Universal Robot dashboard connection and waits for up to `timeout_ms` milliseconds for a response.

Response:

LEScript: Any response received is placed in the variable `ur_dashboard_response`

Java, Python: Function returns any string received or an empty string.

The UR dashboard system provides many commands that are useful in loading, starting, and stopping the robot. The Run tab in LEonard uses `robotmode` to determine whether the robot has booted, and regularly sends `robotmode`, `safetystatus`, and `programstate` to keep an eye on the robot.

When you press the **Robot Mode** button, LEonard cycles through the robot modes as appropriate- RUNNING initiates sending `power off`. IDLE initiates sending `brake release`. And POWER_OFF initiates sending `power on`. This allows you to cycle through UR operating modes.

The **Safety Status** button sends `unlock protective stop and close safety popup` when the robot is in safety stop but not in E-Stop.

The **Program State** button toggles between sending `play` and `stop` to start and stop the loaded PolyScope program. The UR Dashboard device sends a `load JobFile` command when the UR connects with the dashboard to get your default PolyScope program loaded.

A comprehensive discussion of the dashboard interface is available on the UR website:

Using Universal Robots with LEonard

<https://www.universal-robots.com/articles/ur/dashboard-server-e-series-port-29999/>

Here are the handiest ones that are used internally by LEonard!

Useful UR Dashboard Commands

<code>get robot model</code>	Returns robot model number, as in “UR5”
<code>get serial number</code>	Returns robot serial number, for example “20195501xxxx”
<code>PolyscopeVersion</code>	Returns PolyScope version installed on robot
<code>power on</code>	Power system up
<code>brake release</code>	Release from IDLE to READY
<code>load LEonard/LEonard01.urp</code>	Load a PolyScope program (default shown)
<code>play</code>	Start it
<code>close popup</code>	Close a popup prompt on the pendant
<code>close safety popup</code>	Close a safety popup prompt on the pendant
<code>unlock protective stop</code>	Recover from E-stop or safety stop
<code>stop</code>	Stop execution of the program
<code>robotmode</code>	Get mode <code>POWER_OFF</code> <code>POWER_ON</code> <code>BOOTING</code> <code>IDLE</code> <code>RUNNING</code>
<code>programstate</code>	Return program state <code>STOPPED</code> file <code>PLAYING</code> file
<code>power off</code>	Power servos down (and put brakes on)

Using Universal Robots with LEonard

LElib.UR.robot: The UR Robot PolyScope Interface

Lecky Engineering supplies an extensive PolyScope program that supports robot control and grinding functions. This code is supplied with the LEonard installation and must be installed on the UR robot.

Getting robot communications working is discussed in [Basic Ethernet Connection](#) and [The LEonard Interface](#).

Installation of the code on the robot is discussed in [Installing Programs on the UR](#)

```
select_tool(string tool_name)
```

Setup all the necessary environment to be able to use `tool_name`. No motion is performed. Future tool moves, position moves, and grinds will assume this tool is attached.

```
set_part_geometry(string FLAT|CYLINDER|SPHERE, double  
part_diam_mm)
```

Future tool moves and grinds will assume the specified geometry.

```
save_position(position_name)
```

The current robot position is stored in the Positions Table as `position_name`.

```
move_linear(position_name)
```

The robot moves along a linear path to Position `position_name`.

```
move_joint(position_name)
```

The robot performs a joint move to Position `position_name`.

```
move_relative(dx_mm, dy_mm)
```

Move (`dx_mm`, `dy_mm`) relative to current tool position. If the part geometry selected is CYLINDER or SPHERE, robot moves along the part.

```
move_tool_home()
```

Perform a joint move to the home position associated with the current tool.

```
move_tool_mount()
```

Perform a joint move to the mounting position associated with the current tool.

```
free_drive(0=OFF|1=ON)
```

Turn robot free drive mode on or off.

Using Universal Robots with LEonard

The commands below provide a programmatic way to set the default motion parameters.

```
set_linear_speed(speed_mm/s)
```

Sets default linear speed used for robot linear moves.

```
set_linear_accel(accel_mm/s^2)
```

Sets default linear acceleration used for robot linear moves.

```
set_joint_speed(speed_deg/s)
```

Sets default joint speed used for robot joint moves.

```
set_joint_accel(double accel_deg/s^2)
```

Sets default joint acceleration used for robot joint moves.

```
set_blend_radius(double blend_radius_mm)
```

Sets default blend radius used in all robot moves.

```
get_actual_tcp_pose()
```

Ask the current robot to perform `get_actual_tcp_pose()` and return the value in the LEonard variable `actual_tcp_pose`.

```
get_target_tcp_pose()
```

Ask the current robot to perform `get_target_tcp_pose()` and return the value in the LEonard variable `target_tcp_pose`.

```
get_actual_joint_positions()
```

Ask the current robot to perform `get_actual_joint_positions()` and return the value in the LEonard variable `actual_joint_positions`.

```
get_target_joint_positions()
```

Ask the current robot to perform `get_target_joint_positions()` and return the value in the LEonard variable `target_joint_positions`.

```
get_actual_both()
```

Performs both `get_actual_joint_positions()` and `get_actual_tcp_pose()` on the current robot and return the values to the LEonard variables `actual_joint_positions` and `actual_tcp_pose`.

Using Universal Robots with LEonard

```
get_target_both()
```

Performs both `get_target_joint_positions()` **and** `get_target_tcp_pose()` **on the current robot and return the values to the LEonard variables**

`target_joint_positions` **and** `target_tcp_pose`.

```
movej(double j1, j2, j3, j4, j5, j6)
```

Performs a movej to joint positions on the current robot as follows:

```
q = [j1, j2, j3, j4, j5, j6]
```

```
movej(q, a=robot_joint_accel_rpss, v=robot_joint_speed_rps)
```

```
movel(double x, y, z, rx, ry, rz)
```

Performs a movel to a pose on the current robot as follows:

```
p = p[x, y, z, rx, ry, rz]
```

```
movej(q, a=robot_joint_accel, v=robot_joint_speed)
```

```
get_tcp_offset()
```

Ask the current robot to perform `get_tcp_offset()` **and return the value in the LEonard variable** `tcp_offset`.

```
movel_incr_base(double x,y,z,rx,ry,rz)
```

Ask the current robot to move incrementally from the current position in base coordinates as in URScript:

```
local p0 = get_target_tcp_pose()
local p1 = p[x,y,z,dx,dy,dz]
local p2 = pose_add(p0, p1)
if p1[0] == 0 and p1[1] == 0 and p1[2] == 0: # Rotational move
    movel(p2, robot_joint_accel_rpss, robot_joint_speed_rps)
else:
    movel(p2, robot_linear_accel_mpss, robot_linear_speed_mps)
end
```

```
movel_incr_tool(double x,y,z,rx,ry,rz)
```

Ask the current robot to move incrementally from the current position in TCP coordinates as in URScript:

```
local p1 = p[x,y,z,rx,ry,rz]
local p2 = pose_trans(get_target_tcp_pose(), p1)
if p1[0] == 0 and p1[1] == 0 and p1[2] == 0: # Rotational move
    movel(p2, robot_joint_accel_rpss, robot_joint_speed_rps)
else:
    movel(p2, robot_linear_accel_mpss, robot_linear_speed_mps)
end
```


Using Universal Robots with LEonard

`movel_incr_part(x,y,z,rx,ry,rz)`

Ask the current robot to move incrementally from the current position in PART coordinates. X and Y are interpreted based on `set_part_geometry(...)`. For cylinders, X is along the axis of the cylinder and Y is interpreted as a fixed-distance rotation about the cylinder.

`movel_single_axis(axis,value)`

Ask the current robot to move to its current pose with the coordinate `axis` changed to `value`.

`movel_rot_only(rx,ry,rz)`

Ask the current robot to move to its current pose with the new rotations `rx`, `ry`, and `rz`.

`movel_rel_set_tool_origin(double x,y,z,rx,ry,rz)`

`movel_rel_set_tool_origin_here()`

Sets a tool-coordinate origin for the current robot either to a specified pose or to the current robot position. Subsequent calls to `movel_rel_tool()` will move in tool coordinates relative to this origin.

`movel_rel_tool(x,y,z,rx,ry,rz)`

Move to a tool coordinate position that is relative to the `movel_rel_set_tool_origin`.

`movel_rel_set_part_origin(x,y,z,rx,ry,rz)`

`movel_rel_set_part_origin_here()`

Sets a part-coordinate (FLAT, CYLINDER, or SPHERE) origin for the current robot either to a specified pose or to the current robot position. Subsequent calls to `movel_rel_part()` will move in part coordinates relative to this origin.

`movel_rel_part(x,y,z,rx,ry,rz)`

Move to a part coordinate position that is relative to the `movel_rel_set_part_origin`.

`send_robot(string message)`

Sends any command to the Lecky Engineering PolyScope program. All communications with the Lecky Engineering PolyScope program is handled by this command.

1. Commands are sent with a message ID and a checksum as follows:
 - a. (ID, checksum, message)
2. ID can be any integer. LEonard sends an incrementing number between 100 and 999.
3. Checksum is expected to be 1000 – ID.
4. `message` is typically 1 or more comma-separated numeric values.

Using Universal Robots with LEonard

5. The command is non-blocking.
6. The PolyScope program is expected to send a start message:

```
robot_starting = ID
robot_ready = False
```
7. After the command is complete, the PolyScope program is expected to send back the following:

```
robot_response = response_message
robot_ready=True
robot_completed = ID (as it was received)
```

In addition, the UR Command device runs the “general” callback, so the UR robot can return **LeonardMessages** to set variables or trigger other actions in LEonard at any time.

```
set_output(int port, bool value)
```

Set UR digital output `port` to `value`.

```
robot_socket_reset()
```

Commands the Lecky Engineering UR PolyScope program to reset (bounce) its socket connection to LEonard. Program must be running on the UR!

```
robot_program_exit()
```

Commands the Lecky Engineering UR PolyScope program to terminate. Program must be running on the UR!

Low-level Setup Calls

These are all called automatically by `select_tool()`, `set_part_geometry()`, and the `grind_xxx()` functions. They should be used through that high level interface except during testing or for special purposes!

```
set_tcp(x, y, z, rx, ry, rz)
```

Executes `set_tcp(p[x, y, z, rx, ry, rz])` on the current robot only if `x > 10`. Always returns the current `get_tcp_offset()` in the LEonard variable `robot_tcp`.

```
set_payload(mass_kg, cog_x_m, cog_y_m, cog_z_m)
```

Executes `set_paylod(mass_kg, [cog_x_m, cog_y_m, cog_z_m])` on the current robot only if `mass_kg > 0`. Always returns the current `robot_payload_mass_kg` and `robot_paylod_cog_m` in corresponding LEonard variables.

```
set_door_closed_input(int dig_in, int state)
```

Specifies what digital input and state is expected to signify that the door is closed to the current robot.

Using Universal Robots with LLeonard

`set_footswitch_pressed_input(int dig_in, int state)`

Specifies what digital input and state is expected to signify that the footswitch is pressed on the current robot.

`set_tool_on_outputs(int dig_out, int state, ...)`

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `tool_on()` is executed on the current robot.

`set_tool_off_outputs(int dig_out, int state, ...)`

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `tool_off()` is executed on the current robot.

`set_coolant_on_outputs(int dig_out, int state, ...)`

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `coolant_on()` is executed on the current robot.

`set_coolant_off_outputs(int dig_out, int state, ...)`

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `coolant_off()` is executed on the current robot.

`tool_on()`

Performs the `tool_on` output list set in `set_tool_on_outputs()` on the current robot.

`tool_off()`

Performs the `tool_off` output list set in `set_tool_off_outputs()` on the current robot.

`coolant_on()`

Performs the `coolant_on` output list set in `set_coolant_on_outputs()` on the current robot.

`coolant_off()`

Performs the `coolant_off` output list set in `set_coolant_off_outputs()` on the current robot.

LElib.UR.grind: The UR grinding package

The grinding commands use a set of common parameters described below:

`dx_mm, dy_mm, diam_mm`: dimensions of the patterns in mm
`n_cycles`: times to repeat the pattern (ignored if test grinding)

Using Universal Robots with LLeonard

`speed_mm/s`: speed to grind at (ignored if test grinding)
`force_N`: force in Newtons to apply
`stay_in_contact`: 0 to retract at end of grind, 1 to stay in contact

```
grind_line(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N,  
stay_in_contact)
```

```
grind_line_deg(length_mm, angle_deg, n_cycles, speed_mm/s,  
force_N, stay_in_contact)
```

Grind in a straight line centered on the current position, defined either by endpoints or angle.

```
grind_rect(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N,  
stay_in_contact)
```

Grind along a rectangle centered on the current position at the current RZ angle of the tool.

```
grind_serp(dx_mm, dy_mm, n_xsteps, n_ysteps, n_cycles,  
speed_mm/s, force_N, stay_in_contact)
```

Grind a serpentine pattern within a rectangle centered on the current position. `N_xsteps` and `n_ysteps` is the number of moves needed to span the rectangle. One or the other of these must be equal to 1.

```
grind_poly(circle_diam_mm, n_sides, n_cycles, speed_mm/s,  
force_N, stay_in_contact)
```

Grind along a polygon of `n_sides` inscribed in `circle_diam_mm` centered on the current position.

```
grind_circle(circle_diam_mm, n_cycles, speed_mm/s, force_N,  
stay_in_contact)
```

Grind along a circle centered on the current position.

```
grind_spiral(circle1_diam_mm, grind_circle2_diam_mm, n_spirals,  
n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind along a variable diameter circle centered on the current position. The circle goes from the first diameter to the second in `n_spirals` full revolutions.

```
grind_retract()
```

Ensure not in contact with the part. Happens automatically if a non-grind command is sent, if stop or pause is selected, or if `grind_max_wait` timer expires.

Using Universal Robots with LEonard

```
grind_contact_enable(0=Touch OFF,Grind OFF|1=Touch ON,Grind OFF|  
2=Touch ON,Grind ON)
```

Set the grinding mode programmatically as shown.

The commands below provide a programmatic way to set the grinding parameters.

```
grind_touch_retract(touch_retract_mm)
```

Set grind retract speed used after touchoff.

```
grind_touch_speed(touch_speed_mm/s)
```

Set speed used to go in for touchoff in Z.

```
grind_force_dwell(dwell_time_ms)
```

A dwell time performed when force mode is turned on to allow the robot to settle against the grind surface.

```
grind_max_wait(max_time_before_retract_ms)
```

If the tool is left in contact with the surface awaiting the next grind command, it will retract if this timeout is exceeded.

```
grind_max_blend_radius(grind_blend_radius_mm)
```

Sets the maximum blend radius that will be used in any pattern. This will be reduces for small geometries.

```
grind_trial_speed(trial_speed_mm/s)
```

Sets the speed used for “air grinding” when not in Touch + Grind mode.

```
grind_linear_accel(accel_mm/s^2)
```

Sets the linear acceleration used for grinding operations.

```
grind_point_frequency(point_frequency_hz)
```

Sets a point interpolation frequency used for complex figures. Obsolete.

```
grind_jog_speed(trial_speed_mm/s)
```

Sets the speed used when the grinding requires a robot move while not in contact with the part.

```
grind_jog_accel(accel_mm/s^2)
```

Sets the acceleration used for grinding moves not in contact with the part.

Using Universal Robots with LEonard

```
grind_force_mode_damping(damping: 0.0 - 1.0)
```

Sets the UR force_mode_damping parameter to assist in stabilizing force-mode performance.

```
grind_force_mode_gain_scaling(scaling: 0.0 - 2.0)
```

Sets the force_mode_gain_scaling parameter to assist in stabilizing force-mode performance.

Grind User Timers: Internal Use

Enabling these will time each grind operation and place it in a circular buffer of user_timers that can be returned to the variable list with `return_user_timers()`. Used primarily for internal testing.

```
enable_user_timers(integer 0=off, 1=on)
```

Turn the UR-internal user timers on or off.

```
zero_user_timers()
```

Zero all UR-internal user timers.

```
return_user_timers()
```

Return an array of timers. Each timer represents one grinding operation. Repeating the same grinding operations on different surface geometries can be used to validate Lecky Engineering's internal speed calibration system.

LElib.UR.grind Grinding Examples

Here are a few sequences that show the kinds of things that can be done in a recipe. The Examples subdirectory in the Code folder has many more complicated examples that you can examine (and run!).

These examples are shown in LEScript and require slight edits in Java or Python sequences.

```
Remove Current Tool
```

Just remove the current tool from the robot. As long as the one actually mounted is selected, this goes to the tool home followed by the mount/demount position and prompts the operator when it is time to remove.

```
# Remove Current Tool
# Go through demount procedure
# Assumes you have selected whatever tool is actually mounted!

prompt(Please confirm: you wish to demount {robot_tool}?)
```

Using Universal Robots with LLeonard

```
move_tool_home()
move_tool_mount()
prompt(Please demount tool {robot_tool})

select_tool(none)
```

Install A Tool

This goes through prompting to mount a specific tool.

```
# Install 2F85
# Example to install a tool when none is currently installed
# We just select the new tool, move to the mount position, prompt
the operator, and move to tool_home

# Change to whatever tool you like
tool=2F85

# Operator confirmation
prompt(About to mount {tool})

# Mounting process
select_tool({tool}) # This only informs the robot what is
mounted

# This does the physical swap
move_tool_mount()
prompt(Please mount tool {tool})
move_tool_home()
```

Integrated Example

Here we start with the 2F85 tool ready to grind and swap tools and continue from the same location mid-recipe.

```
# Integrated Example
# Assumes we're where we want to grind initially but need to do a
tool swap mid-way

tool1=2F85
tool2=vertest

# Program assumes we are starting with tool1- verify internally
and with operator!
assert(robot_tool,{tool1})
prompt(Confirming tool {tool1} is currently mounted and you are
grinding on {robot_geometry})
```

Using Universal Robots with LLeonard

```
# This will always be our grind_start position
save_position(grind_start)

# Do some grinding with tool1
move_linear(grind_start)
grind_rect(30,30,3,10,10,1)
grind_rect(20,20,3,10,10,1)

prompt(Ready to swap {tool1} to {tool2}?)
# Remove {tool1}
move_tool_home()
move_tool_mount()
prompt(Please remove {tool1})

# Install {tool2}
select_tool({tool2})
move_tool_mount()
prompt(Please install {tool2})
move_tool_home()

# Do some grinding with tool2
move_linear(grind_start) # Returns us to the starting position
grind_rect(30,30,3,10,10,1)
grind_rect(20,20,3,10,10,1)
```

Computed Concentric Circles

Here's a test recipe that grinds 3 concentric circles explicitly and in a loop, not lifting until the final one.

```
# 26 Concentric Circle Test

# Old school
grind_circle(30,2,0.9,10,1)
grind_circle(20,2,0.9,10,1)
grind_circle(10,2,0.9,10,0)

# Do it with a loop
size = 30
count = 2
speed = 0.9
force = 10

repeat:
```


Using Universal Robots with LEonard

```
grind_circle({size},{count},{speed},{force},1)
size -= 10
jump_gt_zero(size,repeat)
```

Lots of Grinds

By pre-teaching points and swapping geometries, a whole day's work could be done (other than tool swaps!)

```
# Test all the patterns on all the geometries

size1=40
size2=10
count=3
speed=5
force=10

select_tool(2F85)
cycleCount=0

redo:
move_linear(demo_flat)

set_part_geometry(FLAT,0)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(CYLINDER,400.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

Using Universal Robots with LLeonard

```
set_part_geometry(CYLINDER,600.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

```
set_part_geometry(CYLINDER,800.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

```
set_part_geometry(CYLINDER,1000.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

```
set_part_geometry(SPHERE,400.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

```
set_part_geometry(SPHERE,600.2)
```

Using Universal Robots with LLeonard

```
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(SPHERE,800.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(SPHERE,1000.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

cycleCount++
jump(redo)
```

INDEX

Ethernet Connection	6	move_linear	14
LElib.UR		move_relative.....	14
dashboard		move_tool_home.....	14
ur_dashboard.....	12	move_tool_mount.....	14
free_drive	14	movej	16
grind		movel	16
enable_user_timers	22	movel_incr_base	16
grind_circle	20	movel_incr_part.....	17
grind_contact_enable.....	21	movel_incr_tool.....	16
grind_force_dwell.....	21	movel_rel_part	17
grind_force_mode_damping	22	movel_rel_set_part_origin	17
grind_force_mode_gain_scaling	22	movel_rel_set_part_origin_here	17
grind_jog_accel.....	21	movel_rel_set_tool_origin	17
grind_jog_speed	21	movel_rel_set_tool_origin_here	17
grind_line	20	movel_rel_tool.....	17
grind_line_deg	20	movel_rot_only.....	17
grind_linear_accel.....	21	movel_single_axis.....	17
grind_max_blend_radius.....	21	position_name.....	14
grind_max_wait.....	21	robot_program_exit.....	18
grind_point_frequency.....	21	robot_socket_reset.....	18
grind_poly	20	save_position	14
grind_rect.....	20	select_tool.....	14
grind_retract.....	20	send_robot.....	17
grind_serp.....	20	set_blend_radius.....	15
grind_spiral	20	set_coolant_on_outputs	19
grind_touch_retract.....	21	set_door_closed_input.....	18
grind_touch_speed	21	set_footswitch_pressed_input.....	19
grind_trial_speed	21	set_joint_accel	15
return_user_timers.....	22	set_joint_speed	15
zero_user_timers	22	set_linear_accel	15
robot		set_linear_speed.....	15
coolant_off	19	set_output	18
coolant_on	19	set_part_geometry	14
get_actual_both	15	set_payload.....	18
get_actual_joint_positions.....	15	set_tcp	18
get_actual_tcp_pose.....	15	set_tool_off_outputs.....	19
get_target_both.....	16	set_tool_on_outputs.....	19
get_target_joint_positions	15	tool_off	19
get_target_tcp_pose	15	tool_on	19
get_tcp_offset	16		