

# Using Universal Robots with LLeonard



LECKY  
ENGINEERING

# Using Universal Robots with LEonard

---

## LEonard Software by Lecky Engineering, LLC

Document Version	Date	Major Additions
21.11.4.0	11/04/2021	Initial user interface and device management system, Java interpreter
22.04.1.0	04/01/2022	Universal Robot interface and grinding system, LEScript support
22.08.1.0	08/15/2022	LMI Gocator interface and demonstration
22.11.1.0	11/14/2022	Python support, screen sizing and display management
22.11.1.1	11/25/2022	Documentation fixes, small code cleanup and reorganization

## CONTENTS

<b>OVERVIEW .....</b>	<b>6</b>
<b>BASIC ETHERNET CONNECTION.....</b>	<b>6</b>
<b>THE LEONARD INTERFACE.....</b>	<b>7</b>
ADDITIONS TO THE RUN TAB FOR UR.....	9
<i>Run Tab- UR Dashboard Connection Only.....</i>	<i>10</i>
<i>Run - UR Dashboard and Command Connection.....</i>	<i>11</i>
<i>UR Grinding Option Controls.....</i>	<i>12</i>
<i>Robot Jogging in LLeonard.....</i>	<i>13</i>
INSTALLING PROGRAMS ON THE UR.....	14
<i>Program Installation Method 1: FTP.....</i>	<i>14</i>
<i>Program Installation Method 2: The Supplied Magic File .....</i>	<i>14</i>
<b>CONTROLLING THE ROBOT.....</b>	<b>16</b>
GENERAL LEONARD.URP COMMUNICATIONS STRATEGY .....	16
<b>LELIB.UR LIBRARY FOR UNIVERSAL ROBOTS.....</b>	<b>16</b>
LELIB.UR.DASHBOARD: FUNCTIONS TO MANAGE THE ROBOT .....	16
string ur_dashboard(string message, int timeout_ms).....	16
LELIB.UR.CONTROL: THE UR ROBOT CONTROL FUNCTIONS.....	18
<i>LElib.UR.control.coremotion: UR Robot Core Motion Functions.....</i>	<i>18</i>
movej(float j1, j2, j3, j4, j5, j6).....	18
get_actual_joint_positions() .....	18
get_target_joint_positions() .....	18
movel(float x, y, z, rx, ry, rz).....	18
movel_single_axis(int axis, float daxis).....	18
movel_rot_only(float rx, ry, rz) .....	18
get_actual_tcp_pose() .....	18
get_target_tcp_pose() .....	19
get_actual_both() .....	19
get_target_both() .....	19
get_tcp_offset() .....	19
set_tcp(float x_m, y_m, z_m, rx_rad, ry_rad, rz_rad) .....	19
set_payload(float mass_kg, cog_x_m, cog_y_m, cog_z_m) .....	19
free_drive(bool enable, int axis 0=base 1=tool 2=part, bool enable_axis1, axis2, axis3, axis4, axis5, axis6) .....	19
<i>LElib.UR.control.incrmove: Incremental Motion Functions.....</i>	<i>20</i>
movel_incr_base(float x,y,z,rx,ry,rz) .....	20
movel_incr_tool(float x,y,z,rx,ry,rz) .....	20
movel_incr_part(x,y,z,rx,ry,rz).....	20
<i>LElib.UR.control.relmove: Relative Motion Functions.....</i>	<i>20</i>
movel_rel_set_tool_origin(float x,y,z,rx,ry,rz).....	20
movel_rel_set_tool_origin_here() .....	20
movel_rel_set_part_origin(float x,y,z,rx,ry,rz) .....	21
movel_rel_set_part_origin_here() .....	21
movel_rel_tool(float x,y,z,rx,ry,rz) .....	21
movel_rel_part(float x,y,z,rx,ry,rz) .....	21
<i>LElib.UR.control.tools: UR Tool Management Functions.....</i>	<i>21</i>

# Using Universal Robots with LLeonard

---

select_tool(string tool_name).....	21
set_tool_on_outputs(int dig_out, int state, ...)	21
set_tool_off_outputs(int dig_out, int state, ...)	21
set_coolant_on_outputs(int dig_out, int state, ...)	21
set_coolant_off_outputs(int dig_out, int state, ...)	21
tool_on().....	21
tool_off() .....	22
coolant_on().....	22
coolant_off() .....	22
<i>LElib.UR.control.positions: UR Position Management Functions</i> .....	22
save_position(string position_name) .....	22
system_position(string position_name, bool is_position).....	22
clear_positions() .....	22
move_joint(string position_name) .....	22
move_linear(string position_name).....	22
move_tool_home().....	22
move_tool_mount().....	22
<i>LElib.UR.control.variables: UR Motion Variables</i> .....	22
set_part_geometry(string FLAT CYLINDER SPHERE, float part_diam_mm) .....	23
set_linear_speed(int speed_mm/s) .....	23
set_linear_accel(int accel_mm/s^2).....	23
set_blend_radius(float blend_radius_mm) .....	23
set_joint_speed(int speed_deg/s) .....	23
set_joint_accel(int accel_deg/s^2).....	23
<i>LElib.UR.control.io: Basic Robot I/O Functions</i> .....	23
set_output(int port, bool value) .....	23
set_door_closed_input(int dig_in, int state).....	23
set_footswitch_pressed_input(int dig_in, int state).....	23
<i>LElib.UR.control.polyscope: Direct PolyScope Communications</i> .....	23
send_robot(string message) .....	23
robot_socket_reset().....	24
robot_program_exit() .....	24
LELIB.UR.GRIND: THE UR GRINDING SYSTEM .....	24
<i>LElib.UR.grind.patterns: Grinding Functions</i> .....	25
grind_contact_enable(int 0=Touch OFF,Grind OFF 1=Touch ON,Grind OFF  2=Touch ON,Grind ON) .....	25
grind_line(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact).....	25
grind_line_deg(length_mm, angle_deg, n_cycles, speed_mm/s, force_N, stay_in_contact).....	25
grind_rect(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact) .....	25
grind_serp(dx_mm, dy_mm, n_xsteps, n_ysteps, n_cycles, speed_mm/s, force_N, stay_in_contact) .....	25
grind_poly(circle_diam_mm, n_sides, n_cycles, speed_mm/s, force_N, stay_in_contact).....	25
grind_circle(circle_diam_mm, n_cycles, speed_mm/s, force_N, stay_in_contact) .....	25
grind_spiral(circle1_diam_mm, grind_circle2_diam_mm, n_spirals, n_cycles, speed_mm/s, force_N, stay_in_contact).....	25
grind_retract() .....	25
<i>LElib.UR.grind.variables: Grinding Control Variables</i> .....	26
grind_touch_retract(int touch_retract_mm) .....	26
grind_touch_speed(int touch_speed_mm/s).....	26
grind_force_dwell(int dwell_time_ms).....	26
grind_max_wait(int max_time_before_retract_ms) .....	26
grind_max_blend_radius(float grind_blend_radius_mm).....	26
grind_trial_speed(int trial_speed_mm/s).....	26
grind_linear_accel(int accel_mm/s^2).....	26

# Using Universal Robots with LEonard

---

grind_point_frequency(int point_frequency_hz).....	26
grind_jog_speed(int trial_speed_mm/s).....	26
grind_jog_accel(int accel_mm/s^2) .....	26
grind_force_mode_damping(float damping: 0.0 – 1.0) .....	26
grind_force_mode_gain_scaling(float scaling: 0.0 – 2.0).....	27
<i>LElib.UR.grind.timers: Internal Engineering Timers</i> .....	27
enable_user_timers(integer 0=off, 1=on) .....	27
zero_user_timers().....	27
return_user_timers() .....	27
LELIB.UR.GRIND GRINDING EXAMPLES.....	27
<i>Remove Current Tool</i> .....	27
<i>Install A Tool</i> .....	28
<i>Integrated Example</i> .....	28
<i>Computed Concentric Circles</i> .....	29
<i>Lots of Grinds</i> .....	30

## Overview

LEonard provides a custom interface for industrial cobots from Universal Robots (UR).


The interface is currently in use with UR-5e and UR-10e robots in many places.

For more information and documentation on the exciting UR product line, see [www.universal-robots.com](http://www.universal-robots.com).

## Basic Ethernet Connection

The UR and the computer running LEonard must have an Ethernet interface capable of communication. At Lecky Engineering, our test machine is on 192.168.0.252/24 and our UR-5e is on 192.168.0.2/24 (`robotIP=192.168.0.2` for us).

You should be able to use `ping robotIP` and `ssh root@robotIP` to verify communication. SSH uses `root` with default password `easybot` on a UR!



```
Command Prompt - ssh root@192.168.0.2
Microsoft Windows [Version 10.0.22621.819]
(c) Microsoft Corporation. All rights reserved.

C:\Users\nedlecky>ping 192.168.0.2

Pinging 192.168.0.2 with 32 bytes of data:
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64
Reply from 192.168.0.2: bytes=32 time<1ms TTL=64

Ping statistics for 192.168.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Users\nedlecky>ssh root@192.168.0.2
root@192.168.0.2's password:
Universal Robots A/S Linux image

Production image
root@ur-20195501059:~# ls
fdisk.script      metadata.n3       polyscope-9.log
firmware          metadata.n3.old  polyscope.log
flightreports     polyscope-10.log putHostnameInHostsFile.py
GUI              polyscope-1.log  robotiq
histogram.properties polyscope-2.log  run_gui.sh
kiosk.sh         polyscope-3.log  starturcontrol.sh
legal_notices    polyscope-4.log  stopurcontrol.sh
list_programs.sh polyscope-5.log  uninstall
log_history.bak  polyscope-6.log  ur-serial
log_history.txt  polyscope-7.log  usbplug.sh
metadata.ini     polyscope-8.log  xsession
root@ur-20195501059:~#
```

Figure 1 Pinging and SSH into a UR to Verify Communication

# Using Universal Robots with LLeonard

If you're like us, you may also want to be able to move files on and off your UR easily. We use WinSCP. Just connect your FTP client to `robotIP:22` and use that `root`, `easybot` login to get access.




Figure 2 WinSCP FTP access to a UR

## The LLeonard Interface

To communicate with the UR, the **Devices** list in LLeonard needs one or two entries for the robot:

1. If you just want to use the UR Dashboard interface and ask the robot to load/run existing PolyScope programs on the robot, you only need a **UrDashboard** device.
2. If you want to use the Lecky Engineering `LEonard01.urp` PolyScope program that allows commanding, driving, and sequencing the robot, as well as using the Lecky Engineering Grinding programs, you also need a **UrCommand** device.

Both devices connect to the same robot, just on different ports.

1. Port 29999 is a standard fixed port that provides dashboard control services on all UR robots. It connects to the robot as a **TcpClient** but has some special features that a basic **TcpClient** device does not.
2. Port 30000 is a custom port used in the Lecky Engineering `LEonard01.urp` PolyScope program. The program looks for a **TcpServer** on the machine running LLeonard. The UrCommand device is a customized **TcpServer** device that has some special features to help with the UR interface.

# Using Universal Robots with LEonard

Devices	Displays	Tools	Robots	General	License							
Connect	Disconnect	Reconnect			Runtime App	Restore		Setup App	Restore		Connect All	Disconnect All
						Minimize			Minimize			
						Exit			Exit			
ID	Name	Enabled	Connected	DeviceType	Address	MessageTag	CallBack	TxPrefix	TxTerminator			
1	UR-5eDash	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrDashboard	192.168.0.2:29999	R.Dash			<C			
2	UR-5eCommand	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrCommand	192.168.0.252:30000	R.Cmd	general		<C			

Figure 3 Device Entries for Universal Robot

It is important to use the `UrCommand` `CallBack` as well as the displayed `TxSuffix` and `RxTerminator`. Default devices that have everything setup just the way we need although you might need to edit the IP address!

The PolyScope job that you wish to be loaded by the `UrDashboard` can be included in the `Jobfile` field of the dashboard device entry. For our example, this is set to `LEonard/LEonard01.urp` since the `LEonard01.urp` program is stored on the robot in `programs/LEonard/LEonard01.urp`.



## Additions to the Run Tab for UR

Special status and control annunciators and buttons appear when a UR is in communication with LEonard. These features are described below:

Annunciators controlled by **UrDashboard**  
(These are talking to the UR.)

Annunciators controlled by **UrCommand**  
**These are talking to the PolyScope program!**

LEonard Rev 22.11.1.0 DEBUG  
11/13/2022 9:21:26 AM

Figure 4 Gocator Status Annunciators

# Using Universal Robots with LEonard

## Run Tab- UR Dashboard Connection Only

Connecting a UR Robot Dashboard makes the robot control annunciators visible:

Devices		Displays		Tools		Grind		General		License													
Connect		Disconnect		Reconnect				Runtime App		Restore				Setup App		Restore				Connect All		Disconnect All	
										Minimize						Minimize							
										Exit						Exit							
▶	ID	Name		Enabled		Connected		DeviceType		Address		MessageTag		CallBack		TxPrefix		TxSuffix		TxType		TxData	
	0	Command		<input checked="" type="checkbox"/>		<input type="checkbox"/>		TcpServer		127.0.0.1:1000		A.CTL		command						<C			
	1	UR-5eDash		<input checked="" type="checkbox"/>		<input checked="" type="checkbox"/>		UrDashboard		192.168.0.2:29999		R.Dash								<C			
	2	UR-5eDash		<input type="checkbox"/>		<input type="checkbox"/>		UrDashboard		192.168.0.2:29999		R.Dash								<C			

Figure 5 LEonard Connected to UR Dashboard

Run	Code	Setup	Logs	Manual001 LEScript Example	New	Save	Save As...	Jog Robot	Exit
<pre># Hello, World! In LEScript UseLEScript() lePrint(Hello, World!) value = 13.25 lePrint(value = {value})</pre>				Current Time		11/5/2022 2:56:00 PM		ENGINEERING User	
				Start Time		11/5/2022 2:29:56 PM		Dashboard OK	
				Total Run Time		00h 00m 00.6s		Robotmode: POWER_OFF	
				STOPPED 005: lePrint(value = 13.25)				Safetystatus: NORMAL	
								STOPPED LEonard01.urp	
				Time in Step		00h 00m 00.1s			
Time Estimate		00h 00m 00.0s							
Time Remaining		00h 00m 00.1s							
Start Step Pause Stop				LEonard Rev 2022.11.5.10 11/5/2022 2:56:00 PM					

Figure 6 LEonard Main Screen when Connected to UR Dashboard

**Dashboard OK:** Shows connection status to the Dashboard (this is a TCP client).

**Robotmode:** Press this to cycle from POWER\_OFF to BOOTING to IDLE to RUNNING

**Safetystatus:** Press this to clear robot stop conditions

**STOPPED/PLAYING:** Use this to toggle between a PolyScope program running or not on the robot. The program loaded is specified in the Device entry and is shown in this button.

Most of these options require that the UR is in Remote mode.

# Using Universal Robots with LEonard

## Run - UR Dashboard and Command Connection

With a UR Command interface also connected, the full UR control system is available. This requires that a special PolyScope program be installed and running on the robot. This program is provided by Lecky Engineering and can be modified by the user if you need special functions. Contact Lecky Engineering for assistance if you are new to UR programming!

The images below assume the optional UR Grinding package is also licensed.

Devices		Displays		Tools		Grind		General		License							
Connect		Disconnect		Reconnect		Runtime App		Restore		Setup App		Restore		Connect All		Disconnect All	
								Minimize				Minimize					
								Exit				Exit					
ID	Name			Enabled	Connected	DeviceType		Address		MessageTag		CallBack		TxPrefix		TxType	
0	Command			<input checked="" type="checkbox"/>	<input type="checkbox"/>	TcpServer		127.0.0.1:1000		A.CTL		command				<	
1	UR-5eDash			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrDashboard		192.168.0.2:29999		R.Dash						<	
2	UR-5eCommand			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	UrCommand		192.168.0.252:30000		R.Cmd		general				<	

Figure 7 LEonard Connected to UR Dashboard and UR Command

Run	Code	Setup	Logs	Manual001 LEScript Example	New	Save	Save As...	Jog Robot	Door Closed	Pedal Up	Exit		
<pre># Hello, World! In LEScript UseLESscript() lePrint(Hello, World!) value = 13.25 lePrint(value = {value})</pre>				Current Time		11/5/2022 3:00:28 PM		ENGINEERING User					
				Start Time		11/5/2022 2:29:56 PM		Dashboard OK		Command Ready			
				Total Run Time		00h 00m 00.6s		Robotmode: RUNNING		Robot Ready			
				STOPPED						Safetystatus: NORMAL		134	
										134			
				Time in Step		00h 00m 00.1s		PLAYING LEonard01.urp		Grind Ready			
				Time Estimate		00h 00m 00.0s		Grind Process					
				Time Remaining		00h 00m 00.1s							
				Grind Cycle		- of							
				Last Z Force		N							
Joint Move to Tool Mount Pose		Joint Move to Tool Home Pose											
sander_mount		sander_home											
Start	Step	Pause	Stop	Touch OFF Grind	2F85	CYLINDER	500	dia (mm)					
				Tool	Part Geom	LEonard Rev 2022.11.5.10 11/5/2022 3:00:28 PM							

Figure 8 LEonard Main Screen when Connected to UR Dashboard and UR Command

**Command Ready:** Shows status of UR Command connection (this is a TCP server).

**Robot Ready:** Shows if the robot is currently executing a LEonard command.

# Using Universal Robots with LEonard

---

**Command Index Numbers:** Shows index number of last command sent and response ID of last response received. These should stay in lockstep and must be equal to allow the next command to be issued in the program.

Tools are selected in the **Tool Dropdown**. More information on Tools is in [Setup - Tools](#)  
Tools have mount and home positions that can be moved into with the **toolname\_mount** and **toolname\_home** buttons.

Part geometry is specified in **Part Geometry Dropdown**: The UR Command program supports surfaces that are FLAT, CYLINDER, or SPHERE

## UR Grinding Option Controls

With the optional Grinding Package enabled we get 2 additional buttons:

**Grind Ready:** Has the current grinding process completed?

**Grind Process:** Are we leaving the tool in contact with the part and expecting the next grind command within a few seconds?

Set the grinding mode with the **Touch/Grind button** which cycles through **No contact**, **Touch Only**, and **Touch+Grind**

**Protective Stops:** These show up in (and may be cleared with) the **SafetyStatus** button

**Door Status** is monitored (IO is configured in the **Setup Tab**). Door Open is treated like **Pause**.

**Footswitch Status** is monitored (IO is configured in the **Setup Tab**).

# Using Universal Robots with LEonard

## Robot Jogging in LEonard

Jogging opens a separate screen. Jogging can be done in **BASE** or **TOOL** coordinates, or relative to a **PART**. The buttons move the robot by the specified increment in Z, XY, or rotation. Holding a button down (mouse) or double-tapping and holding (tablet) makes the move repeat.




Figure 9 UR Jog Dialog

When jogging in **PART** mode, if a cylindrical or spherical geometry is selected, the tool will rotate around the center of the part instead of around the tool tip. This can be convenient for manually jogging to a defect using the touch screen instead of Freedrive

Freedrive is supported in a manner identical to on the UR pendant. The X, Y, X, RX, RY and RZ buttons may be used to enable or disable Freedrive in any desired axis. All, Trans, Plane, and Rot select pre-defined subsets of axes as on the UR.

Coordinate systems may be changed during Freedrive, and the robot will only allow motion relative to the world, the tool, or the center of the part of part geometry is cylinder or sphere. Press the Freedrive button again to turn Freedrive mode off. Saving or exiting the dialog will also turn off Freedrive.

The **Freedrive footswitch** puts all 6 axes in Freedrive whether this jog dialog is open or not.

## Installing Programs on the UR

As an aside, how do we get the programs on the UR? The program needs to wind up on the robot in `programs/LEonard`, and the PolyScope program also requires three somewhat complicated URScript programs to support robot and grinding applications.

### Program Installation Method 1: FTP

We already discussed one method, FTP. Just copy the files from your PC on `sysLEonardRoot/Code/Examples/UR/USBImage-ProgramInstaller/LEonard` onto the robot in `programs/LEonard`.

### Program Installation Method 2: The Supplied Magic File

Another method is to use UR magic files:

1. Make sure your existing robot programs are backed up! This process should not affect them, but it never hurts to be careful.
2. Take a fully erased USB thumb drive and insert it in your PC.
3. Copy all the files and subdirectories from `sysLEonardRoot/Code/Examples/UR/USBImage-ProgramInstaller` onto the thumb drive.
4. Plug the thumb drive into your robot USB port on the pendant- all the necessary files will be installed on your robot in the `programs/LEonard` directory.

***You will likely need to manually open `LEonard01.urp` on your robot to associate it with the installation file you are using in your installation. You'll be prompted to select an installation file. Once you do, resave the program and everything should be automatic from there.***

***There is also a set of three hard-coded IP address that the robot looks at to find LEonard. This allows a robot to be directly tied to only one LEonard. You will have to adjust this if the PolyScope program if your address is something different. Lecky Engineering can help if you need some assistance!***

***The `LEonard01.urp` PolyScope program currently looks for LEonard on:***

***169.254.254.200:30000***

***169.254.254.210:3000***

***192.168.0.252:30000***

# Using Universal Robots with LEonard

---

Connection is initiated by selecting the desired row and pressing **Connect**. In addition, if you have selected **Auto Connect On Load** for your device file, the connection will be started automatically when LEonard starts.

LEonard always starts a UrDashboard connection with a set of commands to initialize the robot, load any specified program, and start it.

```
close safety popup
is in remote control (response must be true)
if JobFile <> ""
    load <Jobfile> (as in Device... default LEonard/LEonard01.urp
    get loaded program (make sure response matches above)
    play
```

Upon successful connection, the `Connected` field should check itself and the UR Status annunciators should appear on the Run tab.

The Run tab in LEonard uses `robotmode` to determine whether the robot has booted, and regularly sends `robotmode`, `safetystatus`, and `programstate` to keep an eye on the robot.

## Controlling the Robot

The UR may be commanded from LEScript, Java, or Python with equal ease.

All three languages provide a set of functions that cover most point-to-point, grinding, and inspection tasks that you might want to do with your cell.

## General LEonard.urp Communications Strategy

The Lecky Engineering PolyScope program supplied for robot sequencing, control, and the grind functions is complex.

Our simple PolyScope program uses large set of underlying URScript code to perform most functions.

That said, UR-savvy users can add their own functions to the PolyScope program with relative ease. All communications between LEonard and the PolyScope program happen over a single socket using a message ID, a simple checksum, and the parameters which are all assumed to be numeric.

All return messages from the robot are asynchronous **LEonardMessages** and can set variables or execute LEScript, Java, or Python functions within LEonard. The whole architecture is quite powerful.

If you need to customize `LEonard01.urp` or the underlying URScript code for your own needs, don't hesitate to contact Lecky Engineering for some start-up assistance!

## LElib.UR Library for Universal Robots

These functions work with Universal Robots robotic systems. The commands fall into three categories

1. Dashboard
2. Command Interface to Lecky Engineering's `LEonard01.urp` PolyScope program
3. Grinding Package for force-controlled surface following

## LElib.UR.dashboard: Functions to Manage the Robot

The UR robot provides a dashboard interface that allows controlling the robot operation.

```
string ur_dashboard(string message, int timeout_ms)
```

Sends the command `message` to the currently selected Universal Robot dashboard connection and waits for up to `timeout_ms` milliseconds for a response.



# Using Universal Robots with LEonard

---

Response:

LEScript: Any response received is placed in the variable `ur_dashboard_response`

Java, Python: Function returns any string received or an empty string.

The UR dashboard system provides many commands that are useful in loading, starting, and stopping the robot. The Run tab in LEonard uses `robotmode` to determine whether the robot has booted, and regularly sends `robotmode`, `safetystatus`, and `programstate` to keep an eye on the robot.

When you press the **Robot Mode** button, LEonard cycles through the robot modes as appropriate- RUNNING initiates sending `power off`. IDLE initiates sending `brake release`. And POWER\_OFF initiates sending `power on`. This allows you to cycle through UR operating modes.

The **Safety Status** button sends `unlock protective stop` and `close safety popup` when the robot is in safety stop but not in E-Stop.

The **Program State** button toggles between sending `play` and `stop` to start and stop the loaded PolyScope program. The UR Dashboard device sends a `load JobFile` command when the UR connects with the dashboard to get your default PolyScope program loaded.

A comprehensive discussion of the dashboard interface is available on the UR website:

<https://www.universal-robots.com/articles/ur/dashboard-server-e-series-port-29999/>

Here are the handiest ones that are used internally by LEonard!

## Useful UR Dashboard Commands

<code>get robot model</code>	Returns robot model number, as in "UR5"
<code>get serial number</code>	Returns robot serial number, for example "20195501xxxx"
<code>PolyscopeVersion</code>	Returns PolyScope version installed on robot
<code>power on</code>	Power system up
<code>brake release</code>	Release from IDLE to READY
<code>load LEonard/LEonard01.urp</code>	Load a PolyScope program (default shown)
<code>play</code>	Start it
<code>close popup</code>	Close a popup prompt on the pendant
<code>close safety popup</code>	Close a safety popup prompt on the pendant
<code>unlock protective stop</code>	Recover from E-stop or safety stop
<code>stop</code>	Stop execution of the program
<code>robotmode</code>	Get mode <code>POWER_OFF</code> <code>POWER_ON</code> <code>BOOTING</code> <code>IDLE</code> <code>RUNNING</code>
<code>programstate</code>	Return program state <code>STOPPED</code> file <code>PLAYING</code> file
<code>power off</code>	Power servos down (and put brakes on)

## LElib.UR.control: The UR Robot Control Functions

Lecky Engineering supplies an extensive PolyScope program that supports robot control and grinding functions. This code is supplied with the LEonard installation and must be installed on the UR robot.

Getting robot communications working is discussed in [Basic Ethernet Connection](#) and [The LEonard Interface](#).

Installation of the code on the robot is discussed in [Installing Programs on the UR](#)

## LElib.UR.control.coremotion: UR Robot Core Motion Functions

```
movej(float j1, j2, j3, j4, j5, j6)
```

Performs a **movej** to **joint positions** on the current robot as follows:

```
q = [j1, j2, j3, j4, j5, j6]
movej(q, a=robot_joint_accel_rpss, v=robot_joint_speed_rps)
```

```
get_actual_joint_positions()
```

Ask the current robot to perform `get_actual_joint_positions()` and return the value in the LEonard variable `actual_joint_positions`.

```
get_target_joint_positions()
```

Ask the current robot to perform `get_target_joint_positions()` and return the value in the LEonard variable `target_joint_positions`.

```
movel(float x, y, z, rx, ry, rz)
```

Performs a **movel** to a **pose** on the current robot as follows:

```
p = p[x, y, z, rx, ry, rz]
movej(q, a=robot_joint_accel, v=robot_joint_speed)
```

```
movel_single_axis(int axis, float daxis)
```

Ask the current robot to move to its current pose with the coordinate `axis` changed to `value`.

```
movel_rot_only(float rx, ry, rz)
```

Ask the current robot to move to its current pose with the new rotations `rx`, `ry`, and `rz`.

```
get_actual_tcp_pose()
```

Ask the current robot to perform `get_actual_tcp_pose()` and return the value in the LEonard variable `actual_tcp_pose`.

# Using Universal Robots with LEonard

---

```
get_target_tcp_pose()
```

Ask the current robot to perform `get_target_tcp_pose()` and return the value in the LEonard variable `target_tcp_pose`.

```
get_actual_both()
```

Performs both `get_actual_joint_positions()` and `get_actual_tcp_pose()` on the current robot and return the values to the LEonard variables `actual_joint_positions` and `actual_tcp_pose`.

```
get_target_both()
```

Performs both `get_target_joint_positions()` and `get_target_tcp_pose()` on the current robot and return the values to the LEonard variables `target_joint_positions` and `target_tcp_pose`.

```
get_tcp_offset()
```

Ask the current robot to perform `get_tcp_offset()` and return the value in the LEonard variable `tcp_offset`.

```
set_tcp(float x_m, y_m, z_m, rx_rad, ry_rad, rz_rad)
```

Executes `set_tcp(p[x,y,z,rx,ry,rz])` on the current robot only if `x > 10`. Always returns the current `get_tcp_offset()` in the LEonard variable `robot_tcp`.

```
set_payload(float mass_kg, cog_x_m, cog_y_m, cog_z_m)
```

Executes `set_payload(mass_kg, [cog_x_m, cog_y_m, cog_z_m])` on the current robot only if `mass_kg > 0`. Always returns the current `robot_payload_mass_kg` and `robot_payload_cog_m` in corresponding LEonard variables.

```
free_drive(bool enable, int axis 0=base|1=tool|2=part, bool enable_axis1, axis2, axis3, axis4, axis5, axis6)
```

Turns the Universal Robots **Free Drive** mode on or off. When on, Free Drive can operate in base, tool, or part coordinate systems and individual axes may be enabled or disabled. Experiment with the Free Drive feature in the Robot Jog dialog to understand how the different setting work.

To use a floor pedal for free drive, define an input in the **Setup | Tools** tab

## LElib.UR.control.incrmove: Incremental Motion Functions

```
move1_incr_base(float x,y,z,rx,ry,rz)
```

Ask the current robot to move incrementally from the current position in base coordinates as in URScript:

```
local p0 = get_target_tcp_pose()
local p1 = p[x,y,z,dx,dy,dz]
local p2 = pose_add(p0, p1)
if p1[0] == 0 and p1[1] == 0 and p1[2] == 0: # Rotational move
    move1(p2, robot_joint_accel_rpss, robot_joint_speed_rps)
else:
    move1(p2, robot_linear_accel_mpss, robot_linear_speed_mps)
end
```

```
move1_incr_tool(float x,y,z,rx,ry,rz)
```

Ask the current robot to move incrementally from the current position in TCP coordinates as in URScript:

```
local p1 = p[x,y,z,rx,ry,rz]
local p2 = pose_trans(get_target_tcp_pose(), p1)
if p1[0] == 0 and p1[1] == 0 and p1[2] == 0: # Rotational move
    move1(p2, robot_joint_accel_rpss, robot_joint_speed_rps)
else:
    move1(p2, robot_linear_accel_mpss, robot_linear_speed_mps)
end
```

```
move1_incr_part(x,y,z,rx,ry,rz)
```

Ask the current robot to move incrementally from the current position in PART coordinates. X and Y are interpreted based on `set_part_geometry(...)`. For cylinders, X is along the axis of the cylinder and Y is interpreted as a fixed-distance rotation about the cylinder.

## LElib.UR.control.relmove: Relative Motion Functions

```
move1_rel_set_tool_origin(float x,y,z,rx,ry,rz)
```

```
move1_rel_set_tool_origin_here()
```

Sets a tool-coordinate origin for the current robot either to a specified pose or to the current robot position. Subsequent calls to `move1_rel_tool()` will move in tool coordinates relative to this origin.

# Using Universal Robots with LLeonard

---

```
move1_rel_set_part_origin(float x,y,z,rx,ry,rz)
```

```
move1_rel_set_part_origin_here()
```

Sets a part-coordinate (FLAT, CYLINDER, or SPHERE) origin for the current robot either to a specified pose or to the current robot position. Subsequent calls to `move1_rel_part()` will move in part coordinates relative to this origin.

```
move1_rel_tool(float x,y,z,rx,ry,rz)
```

Move to a tool coordinate position that is relative to the `move1_rel_set_tool_origin`.

```
move1_rel_part(float x,y,z,rx,ry,rz)
```

Move to a part coordinate position that is relative to the `move1_rel_set_part_origin`.

## LElib.UR.control.tools: UR Tool Management Functions

```
select_tool(string tool_name)
```

Setup all the necessary environment to be able to use `tool_name`. No motion is performed. Future tool moves, position moves, and grinds will assume this tool is attached.

```
set_tool_on_outputs(int dig_out, int state, ...)
```

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `tool_on()` is executed on the current robot.

```
set_tool_off_outputs(int dig_out, int state, ...)
```

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `tool_off()` is executed on the current robot.

```
set_coolant_on_outputs(int dig_out, int state, ...)
```

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `coolant_on()` is executed on the current robot.

```
set_coolant_off_outputs(int dig_out, int state, ...)
```

Sets a set of digital output,state pairs (1 – 4) to specify what outputs should be controlled when `coolant_off()` is executed on the current robot.

```
tool_on()
```

Performs the `tool_on` output list set in `set_tool_on_outputs()` on the current robot.

# Using Universal Robots with LLeonard

---

`tool_off()`

Performs the `tool_off` output list set in `set_tool_off_outputs()` on the current robot.

`coolant_on()`

Performs the `coolant_on` output list set in `set_coolant_on_outputs()` on the current robot.

`coolant_off()`

Performs the `coolant_off` output list set in `set_coolant_off_outputs()` on the current robot.

## LElib.UR.control.positions: UR Position Management Functions

`save_position(string position_name)`

The current robot position (pose and joints) is stored in the Positions Table as `position_name`.

`system_position(string position_name, bool is_position)`

Set `position_name` to be (or not be) a system position. System Positions are not cleared by the simple `clear_positions()` function.

`clear_positions()`

Deletes any positions not marked in the **Code | Positions** table as system positions.

`move_joint(string position_name)`

The robot performs a joint move to the joint positions stored in `position_name`.

`move_linear(string position_name)`

The robot moves along a linear path to the pose stored in `position_name`.

`move_tool_home()`

Perform a joint move to the home position associated with the current tool.

`move_tool_mount()`

Perform a joint move to the mounting position associated with the current tool.

## LElib.UR.control.variables: UR Motion Variables

The commands below provide a programmatic way to set the default motion parameters.

# Using Universal Robots with LEonard

---

```
set_part_geometry(string FLAT|CYLINDER|SPHERE, float  
part_diam_mm)
```

Future tool moves and grinds will assume the specified geometry.

```
set_linear_speed(int speed_mm/s)
```

Sets default linear speed used for robot linear moves.

```
set_linear_accel(int accel_mm/s^2)
```

Sets default linear acceleration used for robot linear moves.

```
set_blend_radius(float blend_radius_mm)
```

Sets default blend radius used in all robot moves.

```
set_joint_speed(int speed_deg/s)
```

Sets default joint speed used for robot joint moves.

```
set_joint_accel(int accel_deg/s^2)
```

Sets default joint acceleration used for robot joint moves.

## LElib.UR.control.io: Basic Robot I/O Functions

```
set_output(int port, bool value)
```

Set UR digital output `port` to `value`.

```
set_door_closed_input(int dig_in, int state)
```

Specifies what digital input and state is expected to signify that the door is closed to the current robot.

```
set_footswitch_pressed_input(int dig_in, int state)
```

Specifies what digital input and state is expected to signify that the footswitch is pressed on the current robot.

## LElib.UR.control.polyscope: Direct PolyScope Communications

These functions are used to message and manage the LEonard01.urp PolyScope program.

```
send_robot(string message)
```

Sends any command to the Lecky Engineering PolyScope program. All communications with the Lecky Engineering PolyScope program is handled by this command.

# Using Universal Robots with LEonard

---

1. Commands are sent with a message ID and a checksum as follows:
  - a. (ID, checksum, message)
2. ID can be any integer. LEonard sends an incrementing number between 100 and 999.
3. Checksum is expected to be  $1000 - \text{ID}$ .
4. message is typically 1 or more comma-separated numeric values.
5. The command is non-blocking.
6. The PolyScope program is expected to send a start message:

```
robot_starting = ID
robot_ready = False
```
7. After the command is complete, the PolyScope program is expected to send back the following:

```
robot_response = response_message
robot_ready = True
robot_completed = ID (as it was received)
```

In addition, the UR Command device runs the `general` Callback, so the UR robot can return **LEonardMessages** to set variables or trigger other actions in LEonard at any time.

```
robot_socket_reset()
```

Commands the Lecky Engineering UR PolyScope program to reset (bounce) its socket connection to LEonard. Program must be running on the UR!

```
robot_program_exit()
```

Commands the Lecky Engineering UR PolyScope program to terminate. Program must be running on the UR!

## LElib.UR.grind: The UR Grinding System

LEonard includes a set of specialty grinding functions that permit force-controlled grinding on flat, cylindrical, and spherical surfaces.

Grinds can move along lines, circles, rectangles, polygons, spirals, and a serpentine pattern along any of the three geometries.

The grinding functions use a set of common parameters described below:

```
dx_mm, dy_mm, diam_mm: dimensions of the patterns in mm
n_cycles: times to repeat the pattern (ignored if test grinding)
speed_mm/s: speed to grind at (ignored if test grinding)
force_N: force in Newtons to apply
stay_in_contact: 0 to retract at end of grind, 1 to stay in contact
```



## LElib.UR.grind.patterns: Grinding Functions

```
grind_contact_enable(int 0=Touch OFF,Grind OFF|1=Touch ON,Grind OFF| 2=Touch ON,Grind ON)
```

Set the grinding mode programmatically as shown.

```
grind_line(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

```
grind_line_deg(length_mm, angle_deg, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind in a straight line centered on the current position, defined either by endpoints or angle.

```
grind_rect(dx_mm, dy_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind along a rectangle centered on the current position at the current RZ angle of the tool.

```
grind_serp(dx_mm, dy_mm, n_xsteps, n_ysteps, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind a serpentine pattern within a rectangle centered on the current position. `n_xsteps` and `n_ysteps` is the number of moves needed to span the rectangle. One or the other of these must be equal to 1.

```
grind_poly(circle_diam_mm, n_sides, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind along a polygon of `n_sides` inscribed in `circle_diam_mm` centered on the current position.

```
grind_circle(circle_diam_mm, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind along a circle centered on the current position.

```
grind_spiral(circle1_diam_mm, grind_circle2_diam_mm, n_spirals, n_cycles, speed_mm/s, force_N, stay_in_contact)
```

Grind along a variable diameter circle centered on the current position. The circle goes from the first diameter to the second in `n_spirals` full revolutions.

```
grind_retract()
```

Ensure not in contact with the part. Happens automatically if a non-grind command is sent, if stop or pause is selected, or if `grind_max_wait` timer expires.

## LElib.UR.grind.variables: Grinding Control Variables

The commands below provide a programmatic way to set the grinding parameters.

```
grind_touch_retract(int touch_retract_mm)
```

Set grind retract speed used after touch off.

```
grind_touch_speed(int touch_speed_mm/s)
```

Set speed used to go in for touch off in Z.

```
grind_force_dwell(int dwell_time_ms)
```

A dwell time performed when force mode is turned on to allow the robot to settle against the grind surface.

```
grind_max_wait(int max_time_before_retract_ms)
```

If the tool is left in contact with the surface awaiting the next grind command, it will retract if this timeout is exceeded.

```
grind_max_blend_radius(float grind_blend_radius_mm)
```

Sets the maximum blend radius that will be used in any pattern. This will be reduced for small geometries.

```
grind_trial_speed(int trial_speed_mm/s)
```

Sets the speed used for “air grinding” when not in Touch + Grind mode.

```
grind_linear_accel(int accel_mm/s^2)
```

Sets the linear acceleration used for grinding operations.

```
grind_point_frequency(int point_frequency_hz)
```

Sets a point interpolation frequency used for complex figures. Obsolete.

```
grind_jog_speed(int trial_speed_mm/s)
```

Sets the speed used when the grinding requires a robot move while not in contact with the part.

```
grind_jog_accel(int accel_mm/s^2)
```

Sets the acceleration used for grinding moves not in contact with the part.

```
grind_force_mode_damping(float damping: 0.0 - 1.0)
```

Sets the UR force\_mode\_damping parameter to assist in stabilizing force-mode performance.

# Using Universal Robots with LEonard

---

```
grind_force_mode_gain_scaling(float scaling: 0.0 - 2.0)
```

Sets the `force_mode_gain_scaling` parameter to assist in stabilizing force-mode performance.

## LElib.UR.grind.timers: Internal Engineering Timers

Enabling these will time each grind operation and place it in a circular buffer of `user_timers` that can be returned to the variable list with `return_user_timers()`. These are used primarily for internal testing. Maintaining proper speed when grinding along lines on cylinders requires a highly non-linear compensation that is computed and implemented internally as the `cyline` package. This is invisible to the user.

```
enable_user_timers(integer 0=off, 1=on)
```

Turn the UR-internal user timers on or off.

```
zero_user_timers()
```

Zero all UR-internal user timers.

```
return_user_timers()
```

Return an array of timers. Each timer represents one grinding operation. Repeating the same grinding operations on different surface geometries can be used to validate Lecky Engineering's internal speed calibration system.

## LElib.UR.grind Grinding Examples

Here are a few sequences that show the kinds of things that can be done in a recipe. The Examples subdirectory in the Code folder has many more complicated examples that you can examine (and run!).

These examples are shown in LEScript and require slight edits in Java or Python sequences.

### Remove Current Tool

Just remove the current tool from the robot. As long as the one actually mounted is selected, this goes to the tool home followed by the mount/demount position and prompts the operator when it is time to remove.

```
# Remove Current Tool
# Go through demount procedure
# Assumes you have selected whatever tool is actually mounted!

prompt(Please confirm: you wish to demount {robot_tool}?)
```

# Using Universal Robots with LEonard

---

```
move_tool_home()
move_tool_mount()
prompt(Please demount tool {robot_tool})

select_tool(none)
```

## Install A Tool

This goes through prompting to mount a specific tool.

```
# Install 2F85
# Example to install a tool when none is currently installed
# We just select the new tool, move to the mount position, prompt
the operator, and move to tool_home

# Change to whatever tool you like
tool=2F85

# Operator confirmation
prompt(About to mount {tool})

# Mounting process
select_tool({tool}) # This only informs the robot what is
mounted

# This does the physical swap
move_tool_mount()
prompt(Please mount tool {tool})
move_tool_home()
```

## Integrated Example

Here we start with the 2F85 tool ready to grind and swap tools and continue from the same location mid-recipe.

```
# Integrated Example
# Assumes we're where we want to grind initially but need to do a
tool swap mid-way

tool1=2F85
tool2=vertest

# Program assumes we are starting with tool1- verify internally
and with operator!
assert(robot_tool,{tool1})
```

# Using Universal Robots with LLeonard

---

```
prompt(Confirming tool {tool1} is currently mounted and you are
grinding on {robot_geometry})

# This will always be our grind_start position
save_position(grind_start)

# Do some grinding with tool1
move_linear(grind_start)
grind_rect(30,30,3,10,10,1)
grind_rect(20,20,3,10,10,1)

prompt(Ready to swap {tool1} to {tool2}?)
# Remove {tool1}
move_tool_home()
move_tool_mount()
prompt(Please remove {tool1})

# Install {tool2}
select_tool({tool2})
move_tool_mount()
prompt(Please install {tool2})
move_tool_home()

# Do some grinding with tool2
move_linear(grind_start) # Returns us to the starting position
grind_rect(30,30,3,10,10,1)
grind_rect(20,20,3,10,10,1)
```

## Computed Concentric Circles

Here's a test recipe that grinds 3 concentric circles explicitly and in a loop, not lifting until the final one.

```
# 26 Concentric Circle Test

# Old school
grind_circle(30,2,0.9,10,1)
grind_circle(20,2,0.9,10,1)
grind_circle(10,2,0.9,10,0)

# Do it with a loop
size = 30
count = 2
speed = 0.9
force = 10
```

```
repeat:
grind_circle({size},{count},{speed},{force},1)
size -= 10
jump_gt_zero(size,repeat)
```

## Lots of Grinds

By pre-teaching points and swapping geometries, a whole day's work could be done (other than tool swaps!)

```
# Test all the patterns on all the geometries

size1=40
size2=10
count=3
speed=5
force=10

select_tool(2F85)
cycleCount=0

redo:
move_linear(demo_flat)

set_part_geometry(FLAT,0)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(CYLINDER,400.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
```

## Using Universal Robots with LLeonard

---

```
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(CYLINDER,600.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(CYLINDER,800.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(CYLINDER,1000.1)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(SPHERE,400.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)
```

## Using Universal Robots with LLeonard

---

```
set_part_geometry(SPHERE,600.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(SPHERE,800.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

set_part_geometry(SPHERE,1000.2)
grind_line({size1},{size2},{count},{speed},{force},1)
grind_line(-{size2},{size1},{count},{speed},{force},1)
grind_rect({size1},{size2},{count},{speed},{force},1)
grind_rect({size2},{size1},{count},{speed},{force},1)
grind_serp({size1},{size1},1,3,{count},{speed},{force},1)
grind_serp({size1},{size1},3,1,{count},{speed},{force},1)
grind_circle({size1},{count},{speed},{force},1)
grind_circle({size2},{count},{speed},{force},1)
grind_spiral({size1},{size2},3,{count},{speed},{force},1)

cycleCount++
jump(redo)
```



## INDEX

Ethernet Connection .....	6	coolant_off.....	22
LElib.Free Drive .....	19	coolant_on.....	22
LElib.UR		select_tool.....	21
control		set_coolant_off_outputs.....	21
coremotion		set_coolant_on_outputs.....	21
free_drive .....	19	set_tool_off_outputs .....	21
get_actual_both.....	19	set_tool_on_outputs .....	21
get_actual_joint_positions .....	18	tool_off.....	22
get_actual_tcp_pose .....	18	tool_on.....	21
get_target_both.....	19	variables	
get_target_joint_positions.....	18	set_blend_radius .....	23
get_target_tcp_pose.....	19	set_joint_accel.....	23
get_tcp_offset.....	19	set_joint_speed .....	23
movej .....	18	set_linear_accel.....	23
movel .....	18	set_linear_speed .....	23
movel_rot_only.....	18	set_part_geometry.....	23
movel_single_axis.....	18	dashboard	
set_payload.....	19	ur_dashboard.....	16
set_tcp .....	19	grind	
incrmove		patterns	
movel_incr_base .....	20	grind_circle .....	25
movel_incr_part.....	20	grind_contact_enable .....	25
movel_incr_tool.....	20	grind_line.....	25
io		grind_line_deg.....	25
set_door_closed_input .....	23	grind_poly.....	25
set_footswitch_pressed_input .....	23	grind_rect .....	25
set_output .....	23	grind_retract .....	25
polyscope		grind_serp .....	25
robot_program_exit .....	24	grind_spiral.....	25
robot_socket_reset.....	24	timers	
send_robot .....	23	enable_user_timers .....	27
positions		return_user_timers .....	27
clear_positions .....	22	zero_user_timers.....	27
move_joint.....	22	variables	
move_linear.....	22	grind_force_dwell .....	26
move_tool_home.....	22	grind_force_mode_damping .....	26
move_tool_mount.....	22	grind_force_mode_gain_scaling .....	27
save_position .....	22	grind_jog_accel .....	26
relmove		grind_jog_speed .....	26
movel_rel_part.....	21	grind_linear_accel .....	26
movel_rel_set_part_origin .....	21	grind_max_blend_radius .....	26
movel_rel_set_part_origin_here .....	21	grind_max_wait .....	26
movel_rel_set_tool_origin.....	20	grind_point_frequency .....	26
movel_rel_set_tool_origin_here.....	20	grind_touch_retract.....	26
movel_rel_tool.....	21	grind_touch_speed .....	26
tools		grind_trial_speed .....	26